



ACR/Summary[®] and ACR/Detail[®]

Installation Guide for IBM[®] i | Release 4.3



Home Office

1240 East Diehl Road, Suite 400

Naperville, IL 60563

Tel: + 1.630.505.1800

www.infogix.com



Infogix, the Infogix checkmark logo, Unitech Systems, Inc., Infogix Assure, Infogix Insight, ACR, ACR/Detail, ACR/Summary, ACR/Workbench, ACR/Connector, ACR/Instream, ACR/File, Information Integrity, and Information With Confidence are registered trademarks of Infogix, Inc.

Infogix ACR, Infogix EM, Infogix ER, Infogix Perceive, Infogix Controls, Infogix Nexix, ACR/TransMatch, and The Information Integrity Experts are trademarks of Infogix, Inc.

Any other trademarks or registered trademarks are the property of their respective owners.

© 2000-2012 Infogix, Inc.

All rights reserved.

Confidential—Limited distribution to authorized persons only, pursuant to the terms of Infogix, Inc. (FKA Unitech Systems, Inc.) license agreement. This document is protected as an unpublished work and constitutes a trade secret of Infogix, Inc.

This document and the information contained herein are the property of Infogix, Inc. Reproduction or use in whole or in part of this document and the information contained herein by anyone without prior written consent of Infogix, Inc. is prohibited.

Publication Number 2055

Publication Date 1/9/12

Contents

Chapter 1 Introduction

System Requirements	5
Contacting Customer Support	6

Chapter 2 Installing ACR/Detail

Installation Steps	7
Step 1: Review Space Requirements	7
Step 2: Create ACR User Profile and Logon as ACR	7
Step 3: Perform the Installation	8
Step 4: Update the Control File	9
Step 5: Install Patches, If Necessary	10
Step 6: Test Your ACR/Detail Installation	10
Step 7: Set Up the Environment	12
Step 8: Specify User Options.....	15

Chapter 3 Installing ACR/Summary

Installation Steps	17
Step 1: Review Space Requirements	17
Step 2: Create ACR User Profile and Logon as ACR	17
Step 3: Perform the Installation	18
Step 4: Update the Control File	19
Step 5: Install Patches, If Necessary	20
Step 6: Test Your ACR/Summary Installation.....	20
Step 7: Set Up the Environment	23
Step 8: Specify User Options.....	26

Contents

Introduction

This guide provides instructions for installing the ACR/Detail and ACR/Summary for the first time.

For instructions on how to upgrade from a previous release, contact Infogix. See “Contacting Customer Support” on page 6.

Audience

This guide is intended for the personnel at your site who will perform the installation or upgrade. A knowledge of system installation is required.

System Requirements

The system requirements are as follows:

ACR/Summary or ACR/Detail for IBM i	
Operating System	IBM i V6R1
Disk Space ¹	ACR/Summary 75 MB ACR/Detail 134 MB

1 - Additional space is required for each production and user environment based on the number of jobs balanced and the amount of historical information saved.

Contacting Customer Support

If you need assistance, contact Infogix Customer Support:

U.S. and Canada: Call us at (630) 505-1890 or send a fax to (630) 505-1883. You can also send e-mail to support@infogix.com.

Outside the U.S. and Canada: Infogix maintains offices around the world. Check our Web site at www.infogix.com for the closest office or e-mail us at support@infogix.com.

Installing ACR/Detail

Installation Steps

The following is an overview of the steps you must perform:

1. "Step 1: Review Space Requirements" in the next section.
2. "Step 2: Create ACR User Profile and Logon as ACR" on page 7
3. "Step 3: Perform the Installation" on page 8
4. "Step 4: Update the Control File" on page 9
5. "Step 5: Install Patches, If Necessary" on page 10
6. "Step 6: Test Your ACR/Detail Installation" on page 10
7. "Step 7: Set Up the Environment" on page 12
8. "Step 8: Specify User Options" on page 15

Step 1: Review Space Requirements

Review the information in "System Requirements" on page 5.

Step 2: Create ACR User Profile and Logon as ACR

ACR/Detail objects are saved with PUBLIC *USE authority. They are owned by ACR. Before installation, it is necessary to create an ACR user profile with *USER rights. Notice in the example below that the authority created is *ALLOBJ. The *ALLOBJ authority is required only for the installation. It is needed because the installation programs require authority to create and restore objects. When the installation is complete, the *ALLOBJ authority can be revoked.

2 ■ Installing ACR/Detail

Installation Steps

For example:

```
CRTUSRPRF USRPRF(ACR)
  USRCLS(*USER)
  SPCAUT(*ALLOBJ *SAVSYS)
  JOBD(DETAIL)
```

Note: The system message “Object Detail in library *LIBL not found” will appear. This informational message indicates that the specified job description for the user profile ACR does not currently exist. However, the user profile (ACR) is still created. The job description for the profile will be restored automatically with the product.

After you enroll User ID ACR in the system distribution directory, logon with User ID ACR.

Step 3: Perform the Installation

Perform the following steps:

1. Make sure you have a system backup before performing the installation.
2. Load ACR/Detail to the IBM i by mounting the installation CD-ROM or cartridge and typing the following command:

```
LODRUN DEV(*OPT)
```
3. When you install ACR/Detail, two main libraries are created. The default names and descriptions are as follows (see the note about renaming libraries below):
 - The program library, `DETAIL`. This contains all of the programs and code for this release.
 - The program change library, `DETAILPC`. This will be populated when you install any future patches (fixes and enhancements) for this release.

Note: About renaming libraries:

During the installation, you have the option of renaming the libraries. If you rename them, the new libraries need to have the same relationship as the original libraries and their names should be used in place of `DETAIL` and `DETAILPC` during the installation process.

For example, if you rename the `DETAIL` and `DETAILPC` libraries to `DTL` and `DTLPC`, respectively, then you should use the `DTL` and `DTLPC` libraries anywhere that `DETAIL` and `DETAILPC` are indicated during the installation procedure.

If libraries with these names already exist, they will be replaced.

4. Press Enter to install ACR/Detail.

If the ACR/Detail installation is successful, the last information entry in the job log will be:

```
INSTALLATION COMPLETE. 2 LIBRARIES RESTORED.
```

Step 4: Update the Control File

The Infogix Control File controls licensing and several global options for ACR/Detail. Before you can run ACR/Detail, it is necessary to update the Control File. To do this, complete the steps below.

1. Execute the following commands:

```
ADDLIBLE DETAILPC *LAST
ADDLIBLE DETAIL *LAST
CALL CUPD
```

The ACR/Detail Installation Control File Update screen will appear.

<i>mm/dd/yy</i>	12:00:00	ACR/Detail Installation	ACR/D <i>releasenum</i>
CUPD		Control File Update	
		User Name: _____	
		Page Size: _____	
		Wait Time: _____	
		F3=Exit	

2. For User Name, enter a user, group, department, or company name that should appear at the top of all ACR/Detail reports.
3. For Page Size, enter the number of report lines to print per page on ACR/Detail output reports. The default is 66 lines per page.
4. For Wait Time, enter the number of seconds the system should wait for a file that is already allocated. The default is 900 seconds.

2 ■ Installing ACR/Detail

Installation Steps

5. Press Enter to update the Control File with your overrides and the license expiration date.

Note: If you are running ACR/Detail during a trial period, the message, Product will expire in ___ days, will appear automatically on the Main Menu. If this message appears after the product has been purchased, call Customer Support using the information in “Contacting Customer Support” on page 6 so that adjustments can be made to the Control File to remove this message.

Step 5: Install Patches, If Necessary

Please log into our password-protected Web site at <http://www.infogix.com/support/default.asp> to download any available patches for this product. Patches come with installation instructions.

If you do not have Internet access, please contact Customer Support for assistance. See “Contacting Customer Support” on page 6.

Step 6: Test Your ACR/Detail Installation

To test your ACR/Detail installation, you will run a sample job and verify that it successfully produces several reports.

1. On the ACR/Detail Main Menu, select 1=Definitions.
2. On the Definitions Main Menu, select 1=Basic Job Information.
3. On the Basic Job Information List, type 9=Run Job next to PHONEEXERCISE and press Enter.
The Execute Reconciliation Job screen (JRUN) will appear.
4. Leave the Cycle Number field blank.
5. If you will run the job in batch, change the Job Queue, Output Queue, and Hold Job options if they are not what you want.
6. Press Enter to run the test job in batch, or F20 to run online.
The job generates the ACRDCNTL, ACRDRCAP, ACRDUSER, and ACRDERROR reports. The reports are shown on the pages that follow. If all the reports are correct, then you have successfully installed the current release.

ACR/D releasenumbr		Reconciliation Control Report			Page 1	
DATE: dd/mm/yy		RECONCILING SUMMARY AND DETAIL FILES			Job ID=PHONEEXERCISE	
TIME: 17.01.59					Cycle#=2011	
ENTRY KEY= 312 2537252						
0315						
A. Internal Control Items:						
Item	Description	Left	Right			
DTLAMT	AMOUNT FROM THE DETAIL CHARGES FILE		\$1.23			
SUMAMT	AMOUNT FROM THE SUMMARY CHARGES FILE	\$1.23				
B. History Items:						
Item	Description	Left	Right			
HIST1	AMOUNT FROM THE DETAIL CHARGES FILE		\$1.23			
----- History Key -----						
312	2537252	Item	Cycle	-Cycle#-		
		DTLAMT	00	00000001		
		RUN DATE: dd/mm/yy	Run Time: 17.01.22			
HIST2	AMOUNT FROM THE SUMMARY CHARGES FILE	\$1.23				
----- History Key -----						
312	2537252	Item	Cycle	-Cycle#-		
		SUMAMT	00	00000001		
		RUN DATE: dd/mm/yy	Run Time: 17.01.22			
C. Calculated Items:						
Item	Calculation Formula	Result				
CALC1	10.00000 + DTLAMT	\$11.23				
CALC2	20.00000 + DTLAMT	\$21.23				
CALC3	30.00000 + DTLAMT	\$31.23				
CALC4	40.00000 + SUMAMT	\$41.23				
D. Rules and Results:						
Item	Rule	Result	Error/Tolerance			
GREATERTHAN	CALC1 > CALC2	**OUT OF BALANCE**	\$10.00-			
LESSTHAN	CALC1 < CALC2	IN BALANCE				
SUMDTL	CALC1 = CALC2	**OUT OF BALANCE**	\$10.00-			
E. Special Instructions:						
Rule Item	Return Code	Instructions				
GREATERTHAN	2000	CALC1 IS NOT GREATER THAN CALC2				
SUMDTL	1000	CALC1 IS NOT EQUAL TO CALC2				
OUT OF BALANCE (Return Code = 2000)						
Environment Library: MARD32ENV				Job Start Date=050315 Job Start Time=17.01.59		
Copyright Infogix, Inc.						

ACR/D releasenumbr		Reconciliation Recap Report			Page 1	
DATE: DD/MM/YY		RECONCILING SUMMARY AND DETAIL FILES			Job ID=PHONEEXERCISE	
TIME: 14.54.28						
Key No.	Key	Cycle #	Status	Code		
1 312	2537252	00000001	**OUT OF BALANCE**	2000		
2 312	3625227	00000001	**OUT OF BALANCE**	2000		
3 312	6834644	00000001	**OUT OF BALANCE**	2000		
4 708	8200252	00000001	**OUT OF BALANCE**	2000		

ACR/D releasenumbr		Reconciliation User Report					Page 1	
DATE: DD/MM/YY		USER REPORT FOR PHONE EXERCISE					Job ID=PHONEEXERCISE	
TIME: 14.54.28								
KEY FIELD	CYCLE ID	INT ITEM	HIST ITEM	CALC ITEM	KEY RTN CD	RUL RTNCD/	RUL ERR/TO	SPEC INSTR
312	00000001	\$1.23	\$1.23	\$11.23	2000	1000	\$10.00-	CALC1 IS N
312	00000001	\$.25	\$.25	\$10.25	2000	1000	\$10.00-	CALC1 IS N
312	00000001	\$28.03	\$28.03	\$38.03	2000	1000	\$10.00-	CALC1 IS N
708	00000001	\$36.51	\$36.51	\$46.51	2000	1000	\$10.00-	CALC1 IS N
			\$66.02	\$106.02			\$40.00-	

2 ■ Installing ACR/Detail

Installation Steps

```
ACR/D releasenumbr                               Page 1
DATE: DD/MM/YY                                Job Control Error Report
TIME: 16.45.04                                RECONCILING SUMMARY AND DETAIL FILES      Job ID=PHONEEXERCISE

Message ID  Msg Sev  Msg Type  Message Text
-----
*** NO  ERRORS ***
```

Step 7: Set Up the Environment

Note: Test and Production Databases: In most applications, several test libraries are established -- one for each user of ACR/Detail. Each library will have its own ACR/Detail databases created when it is defined in environment setup. However, you should normally have only one production database.

Create the User and Production Environments

After installing ACR/Detail, you need to create user and production environments. The user environment is for testing ACR/Detail jobs before moving them into production. The production environment is where all tested jobs will run.

Follow the procedure below to create the user environment. Then, repeat the procedure to create the production environment.

1. Execute the command `ADDLIBLE DETAILPC *LAST`
2. Execute the command `ADDLIBLE DETAIL *LAST`
3. Type `ACRD` on the IBM i command line.
4. On the ACR/Detail Main Menu, select 2=Environment Setup.
5. On the Environment Setup Menu, select 1=Environment Setup.
The Environment Setup File Creation screen will appear. On this screen, you specify the name of an environment library to create.

Then, you can run a job to create the library and several files required by ACR/Detail.

<i>mm/dd/yy</i>	10:31:18	Environment Setup	ACR/D <i>releasenumbr</i>
ENVC		File Creation	
Library Name: _____			
Create Definition Files:	1	1=Yes, 2=No	
Create History File:	1	1=Yes, 2=No	
Job Queue	Output Queue	Hold Job	
<u>QBATCH</u>	<u>PRT01</u>	<u>1</u> 1=Yes, 2=No	
F3=Exit	F20=Run Online		

6. Enter a Library Name for the user or production environment library you want to create.
 7. Accept 1=Yes for Create Definition Files. The definition file will store ACR/Detail job and file definitions required to read inputs, extract and reconcile values, and produce reports.
 8. Accept 1=Yes for Create History File. This file will store all saved ACR/Detail values.
 9. If you will create the environment files in batch, verify the following settings:
 - Job Queue—The name of the job queue to use.
 - Output Queue—Where to direct the Database Initialization Report output by the file creation job.
 - Hold Job—2 will release the job immediately; 1 will hold it on the job queue.
 10. Press Enter to run file creation in batch or F20 to run online.
- Repeat the steps above to create the production environment.

Set Up User Library Lists

The order in which libraries appear on the user and production library lists is important. The order of the libraries determines which files and programs are executed within a job run.

2 ■ Installing ACR/Detail

Installation Steps

When executing ACR/Detail, your library list should look similar to the following:

```
QGPL
QTEMP
*****
User or Production Library (created in previous step)
*****
DETAILPC
DETAIL
```

Hints:

- Put QTEMP above DETAILPC and DETAIL.
- Put the user or production library anyplace above DETAILPC.
- Put DETAIL last.

Assign Privileges to Users

Note: Securing the Production Databases

We recommend that you take steps to secure your installation. At a minimum, protect the databases by allowing read-only access to the production database files for non-production jobs. Assign one or more administrators (usually your change control administrators) to perform quality assurance and migration of definitions from test to production. Only these administrators should have read/write access to the production databases.

Backup and Recovery

The extent to which you provide backups depends upon the disaster recovery procedures at your site.

We recommend that the production databases be included in your normal daily and weekly (incremental and full) backups. In the event of a head crash or similar system failure, backups will allow you to recover the Definition and history databases at least to the state they had been in the night before the failure.

1. Type ACRD on the IBM i command line and press Enter to bring up ACR/Detail.
2. On the ACR/Detail Main Menu, select 2=Environment Setup.
3. On the Environment Setup Menu, select 3=Authorize Optional User Functions.

The Authorize Optional User Functions screen (EAUT) will appear. On this screen, you can authorize users to execute IBM i commands from any menu screen or Next Screen field. You can also authorize

specific users to run jobs online (the F20 option will display on screens where users can run a job online).

mm/dd/yy 15:18:34	Authorize	ACR/D releasenumbr
EAUT	Optional User Functions	
User ID	Activate Commands	Run Online
ACR	<u>Y</u>	<u>Y</u>
QAUTPROF	<u>N</u>	<u>N</u>
QBRMS	<u>N</u>	<u>N</u>
QDBSHR	<u>N</u>	<u>N</u>
QDFTOWN	<u>N</u>	<u>N</u>
QDOC	<u>N</u>	<u>N</u>
QDSNX	<u>N</u>	<u>N</u>
QFIREWALL	N	<u>N</u>
QFNC	<u>N</u>	<u>N</u>
QGATE	<u>N</u>	<u>N</u>
QIJS	<u>N</u>	<u>N</u>
		+
Position to _____		Next Screen _____
F3=Exit		

4. Authorize yourself and other users, as appropriate, to activate commands and run jobs online.
5. Press Enter to save your changes.
6. Press F3 to exit.

Step 8: Specify User Options

ACR/Detail provides system-level “user options” for displaying currency amounts, negative numbers, and dates. These options can be modified to satisfy the reporting needs at your site. In addition, default output queue, job queue, and held job settings can be specified at the system level. The ACR/Detail system administrator can modify these options at any time. The options apply to all environments— they are not specific to the user or production environment. For more information, see the ACR/Detail User Guide for IBM i.

2 ■ Installing ACR/Detail

Installation Steps

Installing ACR/Summary

Installation Steps

The following is an overview of the steps you must perform:

1. "Step 1: Review Space Requirements" in the next section.
2. "Step 2: Create ACR User Profile and Logon as ACR" on page 17
3. "Step 3: Perform the Installation" on page 18
4. "Step 4: Update the Control File" on page 19
5. "Step 5: Install Patches, If Necessary" on page 20
6. "Step 6: Test Your ACR/Summary Installation" on page 20
7. "Step 7: Set Up the Environment" on page 23
8. "Step 8: Specify User Options" on page 26

Step 1: Review Space Requirements

Review the information in "System Requirements" on page 5.

Step 2: Create ACR User Profile and Logon as ACR

ACR/Summary objects are saved with PUBLIC *USE authority. They are owned by ACR. Before installation, it is necessary to create an ACR user profile with *USER rights. Notice in the example below that the authority created is *ALLOBJ. The *ALLOBJ authority is required only for installation. It is needed because the installation programs require authority to create and restore objects. When the installation is complete, the *ALLOBJ authority can be revoked.

3 ■ Installing ACR/Summary

Installation Steps

For example:

```
CRTUSRPRF USRPRF(ACR)
USRCLS(*USER)
SPCAUT(*ALLOBJ *SAVSYS)
JOBDSUMMARY
```

Note: The system message “Object Summary in library *LIBL not found” will appear. This informational message indicates that the specified job description for the user profile ACR does not currently exist. However, the user profile (ACR) is still created. The job description for the profile will be restored automatically with the product.

After you enroll User ID ACR in the system distribution directory, logon with User ID ACR.

Step 3: Perform the Installation

Perform the following steps:

1. Make sure you have a system backup before performing the installation.
2. Load ACR/Summary to the IBM i by mounting the installation CD-ROM or cartridge and typing the following command:

```
LODRUN DEV(*OPT)
```

3. When you install ACR/Summary, two main libraries are created. The default names and descriptions are as follows (see the note about renaming libraries below):

- The program library, SUMMARY. This contains all of the programs and code for this release.
- The program change library, SUMMARYPC. This will be populated when you install any future patches (fixes and enhancements) for this release.

Note: About renaming libraries:

During the installation, you have the option of renaming the libraries. If you rename them, the new libraries need to have the same relationship as the original libraries and their names should be used in place of SUMMARY and SUMMARYPC during the installation process.

For example, if you rename the SUMMARY and SUMMARYPC libraries to SUM and SUMPC, respectively, then you should use the SUM and SUMPC libraries anywhere that SUMMARY and SUMMARYPC are indicated during the installation procedure.

If libraries with these names already exist, they will be replaced.

4. Press Enter to install ACR/Summary.

If the ACR/Summary installation is successful, the last information entry in the job log will be:

```
INSTALLATION COMPLETE. 2 LIBRARIES RESTORED.
```

Step 4: Update the Control File

The Infogix Control File controls licensing and several global options for ACR/Summary. Before you can run ACR/Summary, it is necessary to update the Control File. To do this, complete the steps below.

1. Execute the following commands:

```
ADDLIBLE SUMMARYPC *LAST
ADDLIBLE SUMMARY *LAST
CALL CUPD
```

The ACR/Summary Installation Control File Update screen will appear.

mm/dd/yy	12:00:00	ACR/Summary Installation	ACR/S releasenumbr
CUPD		Control File Update	
		User Name: _____	
		Page Size: _____	
		Wait Time: _____	
		F3=Exit	

2. For User Name, enter a user, group, department, or company name that should appear at the top of all ACR/Summary reports.
3. For Page Size, enter the number of report lines to print per page on ACR/Summary output reports. The default is 66 lines per page.
4. For Wait Time, enter the number of seconds the system should wait for a file that is already allocated. The default is 900 seconds.

3 ■ Installing ACR/Summary

Installation Steps

5. Press Enter to update the Control File with your overrides and the license expiration date

Note: If you are running ACR/Summary during a trial period, the message, Product will expire in ___ days, will appear automatically on the Main Menu. If this message appears after the product has been purchased, call Customer Support using the information in “Contacting Customer Support” on page 6.

Step 5: Install Patches, If Necessary

Please log into our password-protected Web site at <http://www.infogix.com/support/default.asp> to download any available patches for this product. Patches come with installation instructions.

If you do not have Internet access, please contact Customer Support for assistance. See “Contacting Customer Support” on page 6.

Step 6: Test Your ACR/Summary Installation

To test your ACR/Summary installation, you will run two sample jobs and verify that they successfully produce several reports.

1. Execute the command CALL PRINTRPTS to create reports in the ACROUTQ output queue in the SUMMARY library.
2. On the ACR/Summary Main Menu, select 1=Job Definitions.
3. On the Job Definition Main Menu, select 1=Basic Job Information.
4. On the Basic Job Information List, type 9=Run Job next to JOBXYZ EDIT and press Enter.

The File Interface Interactive Mode screen (FINT) will appear.

5. If you will run the job in batch, change the Job Queue, Output Queue, and Hold Job options if they are not what you want.
6. Run the test job twice, using consecutive cycle numbers (for example, 20111024 and 20111025). Press Enter to run it in batch, or F20 to run online.

The job should generate the Balancing Control Report (ACRSCNTL) and Job Control Error Report (ACRSERROR) shown on the next two pages. The Balancing Control Report should look

similar to the one shown. The Job Control Error Report should show the job ran with “No Errors.”

ACR/S releasenumbr		BALANCING CONTROL REPORT		PAGE 001
DATE: dd/mm/yy		Monthly File Edit System		
TIME: 09.43.46		JOB=JOBXYZ	STEP=EDIT	QUAL=
		CYCLE# = 20110616 RUN# = 001		
A. INTERNAL CONTROL ITEMS:				
ITEM NO.	DESCRIPTION	INPUT	Right Heading	
I-001.	Input Transactions			9,867
I-002.	Valid Transactions			9,800
I-003.	Invalid Transactions			23
I-004.	Add Transactions			2,000
I-005.	Delete Transactions	1,900		
I-006.	Change Transactions	5,900-		
I-007.	Calculated Rule Example	\$7,104.24-	CALCULATED	C-001
B. EXTERNAL CONTROL ITEMS:				
NONE.				
C. CALCULATED ITEMS:				
ITEM NO.	CALCULATION FORMULA	RESULT	CALC MESSAGE	
C-001.	-.72000 * I-001	\$7,104.24-		
D. BALANCING RULES & RESULTS:				
RULE NO.	BALANCING RULE	RESULT	ERROR/TOLERANCE	
1.	I-001 EQ I-002 + I-003	OUT OF BALANCE	44.00	
2.	I-002 EQ I-004 + I-005 + I-006	OUT OF BALANCE	11,800.00	
3.	70.00000 EQ I-003	OUT OF BALANCE	47.00	
4.	IF R-001 OR R-002 TRUE THEN PROCESS R-003	ACTION BYPASS		
E. SPECIAL INSTRUCTIONS:				
RULE NO.	RETURN CODE	INSTRUCTIONS		
1.	3002	Call George		
2.	3002	Call George		
3.	0000	NONE.		
		OUT OF BALANCE	(RETURN CODE = 3002)	
ENVIRONMENT LIBRARY: NEWLIB32		JOB START DATE=11/06/16 JOB START TIME=09.43.46		
Copyright Infoglix, Inc.				

ACR/S releasenumbr		Job Control Error Report		Page 1
DATE: dd/mm/yy		Monthly File Edit System		
TIME: 09.43.46		Job ID=JOBXYZ	EDIT	
Message ID	Msg Sev	Msg Type	Message Text	
			*** N O E R R O R S ***	

3 ■ Installing ACR/Summary

Installation Steps

7. On the Basic Job Information List, type 9=Run Job next to JOBXYZ UPDATE and press Enter.
The File Interface Interactive Mode screen (FINT) will appear.
8. If you will run the job in batch, change the Job Queue, Output Queue, and Hold Job options if they are not what you want. Use the cycle number that you used for the second run of JOBXYZ EDIT in step 6 on page 20.
9. Press Enter to run the job in batch, or F20 to run online.
The job should generate the Balancing Control Report (ACRSCNTL) and Job Control Error Report (ACRSERROR) shown on the next two pages. The Balancing Control Report should look similar to the one shown. The Job Control Error Report should show the job ran with “No Errors.”

ACR/S <i>releasename</i>										PAGE 001		
DATE: dd/mm/yy												
TIME: 14.19.59												
BALANCING CONTROL REPORT												
Monthly File Update System												
JOB=JOBXYZ STEP=UPDATE QUAL=												
CYCLE#=20110310 RUN#=001												
A. INTERNAL CONTROL ITEMS:												
ITEM NO.	DESCRIPTION									Left Heading	Right Heading	
I-001.	Old Master Records									100,300		
I-002.	New Master Records									100,400		
I-003.	Valid Transactions										9,800	
B. HISTORY ITEMS:												
ITEM NO.	JOB	STEP	QUAL	ITEM	CYCLE	CYCLE#	RUN#	RUNDATE	RUNTIME	PROGRAM	Left Heading	Right Heading
E-001.	report total from previous day											9,867
	JOBXYZ	EDIT		001	-001	20110310	000	11/03/10	14.19.33			
E-002.	JOBXYZ EDIT 004 -001 20110310 000 11/03/10 14.19.33											2,000
E-003.	JOBXYZ EDIT 005 -001 20110310 000 11/03/10 14.19.33											1,900
E-004.	JOBXYZ EDIT 002 -009 20110310 000 11/03/10 14.19.33											
											19,600	
C. CALCULATED ITEMS:												
ITEM NO.	CALCULATION FORMULA									RESULT		
C-001.	I-001 + E-001 - E-003									108,267		
D. BALANCING RULES & RESULTS:												
RULE NO.	BALANCING RULE									RESULT	ERROR/TOLERANCE	
1.	I-001 EQ E-001									**OUT OF BALANCE**	90,433	
2.	I-002 EQ C-001									**OUT OF BALANCE**	-7,867-	
3.	I-003 EQ E-004									**OUT OF BALANCE**	-9,800-	
E. SPECIAL INSTRUCTIONS:												
RULE NO.	CODE	INSTRUCTIONS										
1.	3021	Call Sally ASAP										
2.	3022	Call Tracy										
3.	3023	Call Mr. Bush										
ENVIRONMENT LIBRARY: NEWLIB32										OUT OF BALANCE (RETURN CODE = 3023)		
Copyright Infogix, Inc.										JOB START DATE=11/03/10 JOB START TIME=14.19.59		

Step 7: Set Up the Environment

Note: Test and Production Databases: In most applications, several test libraries are established -- one for each user of ACR/Detail. Each library will have its own ACR/Detail databases created when it is defined in environment setup. However, you should normally have only one production database.

Create the User and Production Environments

After installing ACR/Summary, you need to create user and production environments. The user environment is for testing ACR/Summary jobs before moving them into production. The production environment is where all tested jobs will run.

Follow the procedure below to create the user environment. Then, repeat the procedure to create the production environment.

1. Execute the command ADDLIBLE SUMMARYPC *LAST
2. Execute the command ADDLIBLE SUMMARY *LAST
3. Type ACR on the IBM i command line.
4. On the ACR/Summary Main Menu, select 5=Environment Setup.
5. On the Environment Setup Menu, select 1=Environment Setup.
The Environment Setup File Creation screen will appear. On this screen, you specify the name of an environment library to create. Then, you can run a job to create the library and several files required by ACR/Summary.

<i>mm/dd/yy</i>	10:31:18	Environment Setup	<i>ACR/S releasenumbr</i>
ENVC		File Creation	
Library Name: _____			
Create Definition Files:	1	1=Yes, 2=No	
Create History File:	1	1=Yes, 2=No	
Job Queue	Output Queue	Hold Job	
<u>QBATCH</u>	<u>PRT01</u>	<u>1</u> 1=Yes, 2=No	
F3=Exit	F20=Run Online		

3 ■ Installing ACR/Summary

Installation Steps

6. Enter a Library Name for the user or production environment library you want to create.
7. Accept 1=Yes for Create Definition Files. The definition file will store ACR/Summary job and file definitions required to read inputs, extract and balance values, and produce reports.
8. Accept 1=Yes for Create History File. This file will store all saved ACR/Summary values.
9. If you will create the environment files in batch, verify the following settings:
 - Job Queue—The name of the job queue to use.
 - Output Queue—Where to direct the Database Initialization Report output by the file creation job.
 - Hold Job—2 will release the job immediately; 1 will hold it on the job queue.
10. Press Enter to run file creation in batch or F20 to run online.

Repeat the steps above to create the production environment.

Set Up User Library Lists

The order in which libraries appear on the user and production library lists is important. The order of the libraries determines which files and programs are executed within a job run.

When executing ACR/Summary, your library list should look similar to the following:

```
QGPL
QTEMP
*****
User or Production Library (created in previous step)
*****
SUMMARYPC
SUMMARY
```

Hints:

- Put QTEMP above SUMMARYPC and SUMMARY.
- Put the user or production library anyplace above SUMMARYPC.
- Put SUMMARY last.

Assign Privileges to Users

Note: Securing the Production Databases

We recommend that you take steps to secure your installation. At a minimum, protect the databases by allowing read-only access to the production database files for non-production jobs. Assign one or more administrators (usually your change control administrators) to perform quality assurance and migration of definitions from test to production. Only these administrators should have read/write access to the production databases.

Backup and Recovery

The extent to which you provide backups depends upon the disaster recovery procedures at your site.

We recommend that the production databases be included in your normal daily and weekly (incremental and full) backups. In the event of a head crash or similar system failure, backups will allow you to recover the Definition and history databases at least to the state they had been in the night before the failure.

-
1. Type ACR on the IBM i command line and press Enter to bring up ACR/Summary.
 2. On the ACR/Summary Main Menu, select 5=Environment Setup.
 3. On the Environment Setup Menu, select 4=Authorize Optional User Functions.

The Optional User Functions screen (EAUT) will appear. On this screen, you can authorize users to execute IBM i commands from any menu screen or Next Screen field. You can also authorize

3 ■ Installing ACR/Summary

Installation Steps

specific users to run jobs online (the F20 option will display on screens where users can run a job online).

<u>User ID</u>	<u>Activate Commands</u>	<u>Run Online</u>	
ACR	<u>Y</u>	<u>Y</u>	
QAUTPROF	<u>N</u>	<u>N</u>	
QBRMS	<u>N</u>	<u>N</u>	
QDBSHR	<u>N</u>	<u>N</u>	
QDFTOWN	<u>N</u>	<u>N</u>	
QDOC	<u>N</u>	<u>N</u>	
QDSNX	<u>N</u>	<u>N</u>	
QFIREWALL	<u>N</u>	<u>N</u>	
QFNC	<u>N</u>	<u>N</u>	
QGATE	<u>N</u>	<u>N</u>	
QIJS	<u>N</u>	<u>N</u>	+

mm/dd/yy 15:18:34 ACR/Summary Authorization ACR/S releasenumbr
EAUT Optional User Functions

Position to _____ New Screen _____
F3=Exit

4. Authorize yourself and other users, as appropriate, to activate commands and run jobs online.
5. Press Enter to save your changes.
6. Press F3 to exit.

Step 8: Specify User Options

ACR/Summary provides system-level “user options” for displaying currency amounts, negative numbers, and dates. These options can be modified to satisfy the reporting needs at your site. In addition, default output queue, job queue, and held job settings can be specified at the system level. The ACR/Summary system administrator can modify these options at any time. The options apply to all environments—they are not specific to the user or production environment. For more information, see the ACR/Summary User Guide for IBM i.