

ACR/Summary[®] and ACR/Detail[®]

Installation Guide

For Windows[®]
Release 4.1



Home Office
1240 East Diehl Road, Suite 400
Naperville, IL 60563
Tel: + 1.630.505.1800

www.infogix.com

Infogix, the Infogix checkmark logo, Unitech Systems, Inc., Infogix Assure, Infogix Insight, ACR, ACR/Detail, ACR/Summary, ACR/File, Information Integrity, and Information With Confidence are registered trademarks of Infogix, Inc.

Infogix ACR, Infogix EM, Infogix ER, Infogix Controls, ACR/Connector, ACR/Instream, ACR/TransMatch, ACR/Workbench, and The Information Integrity Experts are trademarks of Infogix, Inc.

Any other trademarks or registered trademarks are the property of their respective owners.

Copyright 1998-2009 Infogix, Inc. All rights reserved.

Confidential—Limited distribution to authorized persons only, pursuant to the terms of Infogix, Inc. (FKA Unitech Systems, Inc.) license agreement. This document is protected as an unpublished work and constitutes a trade secret of Infogix, Inc.

This document and the information contained herein are the property of Infogix, Inc. Reproduction or use in whole or in part of this document and the information contained herein by anyone without prior written consent of Infogix, Inc. is prohibited.

Publication Number 1549

Publication Date 6/3/09

Contents

Chapter 1 Introduction

About This Guide.....	5
Contacting Customer Support	6

Chapter 2 Installing ACR/Summary and ACR/Detail Server

System Requirements for the Server	7
Overview of Server and Client Installation and Setup Steps	8
Installing the CD	9
Increase the Maximum File Size (Optional).....	11
Installing the Net Express Licensing Key	11

Chapter 3 Configuring and Licensing the Server

Creating a Logon Account on Windows 2000 Server.....	13
Creating a Logon Account on Windows Server 2003 or XP	18
Setting and Modifying Server Properties	24
Implementing and Maintaining Your Licensing	29
Upgrading from a Pre-Release 4.0 Release.....	38

Chapter 4 Installing a Client

Before You Begin.....	39
System Requirements for a Client.....	39
Steps for Installing a Client	40

Chapter 5 Installing and Licensing ACR/Workbench

 System Requirements for ACR/Workbench 41

 Overview of ACR/Workbench Installation and Setup Steps 42

 Uninstall the Previous Release if Appropriate 42

 Installing the CD 42

 Installing the Net Express Licensing Key 43

 Upgrading from a Pre-Release 4.0 Release..... 44

 Using ACR/Workbench..... 44

Chapter 6 Upgrading from a Pre-Release 4.0 Release

 Upgrading ACR/Summary for Windows 45

 Upgrading ACR/Detail for Windows 49

Index 53

Introduction

This chapter provides an overview to this guide and includes the following sections:

- “About This Guide” on page 5
- “Contacting Customer Support” on page 6

About This Guide

This guide provides installation and licensing instructions for the following products

- ACR/Summary and ACR/Detail Server and Clients.
- ACR/Workbench.

Audience

This guide is intended for the person who will install and/or upgrade the products listed above.

Organization of Information

Chapter 1, “Introduction” describes the components of the guide and provides information for contacting Customer Support.

Chapter 2, “Installing ACR/Summary and ACR/Detail Server” includes system requirements and instructions for installing the Server and, for first-time installations, installing the Net Express licensing key.

Chapter 3, “Configuring and Licensing the Server” explains how to configure the server and how to activate and maintain your licensing.

Chapter 4, “Installing a Client” includes system requirements and instructions for installing ACR/Summary Client or ACR/Detail Client.

Chapter 5, “Installing and Licensing ACR/Workbench” provides system requirements and instructions for installing and licensing ACR/Workbench.

Chapter 6, “Upgrading from a Pre-Release 4.0 Release” provides instructions for upgrading ACR/Summary and ACR/Detail Server and ACR/Workbench from a release previous to Release 4.0.

Contacting Customer Support

If you need assistance, contact Infogix Customer Support:

U.S. and Canada: Call us at (630) 505-1890 or send a fax to (630) 505-1883. You can also send e-mail to support@infogix.com.

Outside the U.S. and Canada: Infogix maintains offices around the world. Check our Web site at www.infogix.com for the closest Infogix office or e-mail us at support@infogix.com.

Installing ACR/Summary and ACR/Detail Server

This chapter provides directions for installing ACR/Summary and ACR/Detail Server. It contains the following sections:

- [System Requirements for the Server](#) - page 7
- [Overview of Server and Client Installation and Setup Steps](#) - page 8
- [Installing the CD](#) - page 9
- [Increase the Maximum File Size \(Optional\)](#) - page 11
- [Installing the Net Express Licensing Key](#) - page 11

System Requirements for the Server

Following are the minimum system requirements for the ACR/Summary and ACR/Detail Server:

Category	Requirement
Hardware and Operating System	IBM or compatible machine with Microsoft Windows 2000 Server, Windows Server 2003, or Windows XP
Memory	At least 64 MB of Random Access Memory (RAM)
Disk Space	A hard drive with at least 50 MB of free space
Drive	CD-ROM
Network Communication	TCP/IP protocol

If you need other system requirements, see the following sections:

- [“System Requirements for a Client”](#) on page 39
- [“System Requirements for ACR/Workbench”](#) on page 41

Overview of Server and Client Installation and Setup Steps

The steps for installation and setup of the ACR/Summary and ACR/Detail Server and Client(s) are as follows. Where additional detail is needed, the steps provide references to the appropriate sections.

1. Before installing the server, do the following:
 - Ensure that you have an ACR/Summary and ACR/Detail Server installation CD.
 - Ensure that you have administrator rights for the system where you will install ACR/Summary and ACR/Detail Server.
 - Verify that the system where you plan to install the server meets the requirements described in the next section.
 - Determine whether you will use dual install, as described in the next step.
2. If you are upgrading from a previous release, uninstall the old release only if appropriate:
 - If you want to install and test the new release of the Server while continuing to support the old release (this is called a dual install), do not uninstall the old release.
 - If you do not want to perform a dual install, stop the service on the Server Properties dialog box and uninstall ACR/Summary and ACR/Detail Server using the **Add or Remove Programs** option on the Control Panel.
3. Insert the ACR/Summary and ACR/Detail Server CD and follow the wizard prompts (see “Installing the CD” on page 9).
4. Increase the maximum file size if appropriate (see “Increase the Maximum File Size (Optional)” on page 11).
5. If this is the first installation of ACR/Summary and ACR/Detail Server, install the licensing key (see “Installing the Net Express Licensing Key” on page 11).
6. If this is the first installation of ACR/Summary and ACR/Detail Server, create a New User account for the Server that will be used to log on to the service, start and stop the Server, configure the Server, and activate and maintain the licensing (see “Creating a Logon Account on Windows 2000 Server” on page 13 or “Creating a Logon Account on Windows Server 2003 or XP” on page 18).

7. Set up or modify properties of the Server in the Server Properties dialog box (see “Setting and Modifying Server Properties” on page 24.)
8. Implement or update your licensing as appropriate. See “Implementing and Maintaining Your Licensing” on page 29.
9. If you are upgrading from a release previous to Release 4.0, you must follow the instructions for your product in “Upgrading from a Pre-Release 4.0 Release” on page 45.
10. If you are installing an upgrade, uninstall existing clients using the **Add or Remove Programs** option on the Control Panel.
11. Install the ACR/Summary Client and/or ACR/Detail Client on user PCs (see “Steps for Installing a Client” on page 40).

Installing the CD

Note: Before you begin, review the “Overview of Server and Client Installation and Setup Steps” above. Ensure that you have uninstalled the previous release only if you do not want to use the dual install feature described in step 2 on page 8.

1. Insert the ACR/Summary and ACR/Detail Server installation CD in the CD-ROM drive on the machine that will be the server. Normally, the installation program starts automatically. If it does not, run the **setup.exe** program on the CD.
2. On the Welcome page, click **Next**.
3. On the Select Destination Directory page, accept the default installation directory, or browse for the directory you prefer. The default installation path is: **C:\Infogix\SumDetServer**.
4. Click **Next**.
5. On the Communication Parameters page, accept the defaults for the administration and user port numbers, or enter the port numbers that apply in your environment.
The **Administration port number** is used for starting and stopping the ACR/Summary and ACR/Detail Server.
The **User port number** is used by the clients to communicate requests to the server for ACR/Summary and ACR/Detail services. Some examples of ACR/Summary services are updating the

2 ■ Installing ACR/Summary and ACR/Detail Server

Installing the CD

definition database and performing balancing. ACR/Detail services include updating the definition database and performing reconciliation

Note: The user port number you enter here must also be entered in the Add/Edit Configuration dialog box of the ACR/Summary and/or ACR/Detail Client on the user's PC.

Typically, the default port numbers are not in use by any common protocol such as FTP, SMTP, SNMP, or HTTP. However, another software product installed on your system may use these ports. If this is the case, you will need to select different port numbers that are not already assigned to another service.

The Administrative and User Port numbers must be different. For instance, you cannot enter 3000 for both. Valid port numbers are between 1 and 65535.

6. Click **Next**.
7. On the Log File Options page, if you want the ACR/Summary and ACR/Detail Server to log the processing messages that it issues, make sure that the **Write messages to log file** check box is marked. By default, the ACR/Summary and ACR/Detail Server will log messages in the **SumDetSv.log** file. The log file will be located in the same folder where the ACR/Summary and ACR/Detail Server is installed. If you prefer to save the log file in a different folder, click **Browse**. Messages will be retained in the log file for 30 days, unless you specify a different time period.
8. Click **Next** to review the installation parameters.
9. If you are satisfied with the information shown, click **Next** to perform the installation. Otherwise, click **Back** to go back to previous pages so you can change the installation parameters. You can also change settings for the Communication and Logging parameters after installation through the Server Properties dialog box. See [“Setting and Modifying Server Properties”](#) on page 24.
10. When the Installation Completed page appears, click **Finish** to complete the installation.
11. If you are prompted to restart the computer, click OK in the Install dialog box. Otherwise, restart your computer after you have completed [Chapter 3, “Configuring and Licensing the Server.”](#)

You can now proceed to the next section, "[Installing the Net Express Licensing Key](#)."

Increase the Maximum File Size (Optional)

ACR/Summary and ACR/Detail ship with environment variable FILEMAXSIZE=4. This setting will be appropriate for users who always use a file input size of 4GB or less. If you use input files greater than 4GB, you will have to override this value by setting FILEMAXSIZE=8 (no limit) in the extfh configuration file.

To override the environment variable FILEMAXSIZE, create the file extfh.cfg, and add the following two lines:

```
[XFH-DEFAULT]
FILEMAXSIZE=8
```

Then, modify the batch run .skl or .bat file to set the new variable. Add a line after the SET COBCPY= command line:

For ACR/Detail, add:

```
SET EXTFH=C:\Infogix\Detail32\extfh.cfg
```

For ACR/Summary, add:

```
SET EXTFH=C:\Infogix\Summary32\extfh.cfg
```

Installing the Net Express Licensing Key

If this is the first installation of an ACR/Summary and ACR/Detail Server, you must install the licensing key. If you know the proper licensing key is already installed, skip this section.

Note: After the licensing key is installed, you will still need to implement and maintain your licensing. Instructions will be provided in the next chapter in the section "[Implementing and Maintaining Your Licensing](#)" on page 29.

To install the licensing key, do the following:

1. Use Windows Explorer to display the contents of the ACR/Summary and ACR/Detail Server folder that you installed in [step](#) on page 9. The default location is as follows:

```
C:\Infogix\SumDetServer
```

2. Open the application server subfolder.

```
C:\Infogix\SumDetServer\appserv
```

2 ■ Installing ACR/Summary and ACR/Detail Server

Installing the Net Express Licensing Key

3. Select **setup.exe** to launch the Micro Focus Application Server for Net Express 4.0 Setup wizard.
If you need to install the licensing key, the setup program wizard will prompt you through the process, as described in the next step.
If you already have the proper licensing key installed, an “Application Server For Net Express 4.0 is already Installed” dialog box displays. Click **No** at the upgrade option, and **OK** at the second dialog box that displays.
4. To proceed with the licensing setup, follow the instructions on the screen and accept the default settings.

Note: Infogix recommends accepting the default location for the licensing files. The licensing files cannot be in the same location as the ACR/Summary and ACR/Detail Server.

5. Call Customer Support when you reach the License Registration dialog box. See “Contacting Customer Support” on page 6. A representative will give you a serial number and a license number to enter in the dialog box.
6. Once you have entered the numbers, click **OK**. Then, click Next until the following message displays:

License installed OK

Click **OK**, again. Then, click **Next** until the Setup Completed dialog box displays.

Configuring and Licensing the Server

This chapter provides instructions for configuring and licensing ACR/Summary Server and ACR/Detail Server. It contains the following sections:

- “Creating a Logon Account on Windows 2000 Server” on page 13
- “Creating a Logon Account on Windows Server 2003 or XP” on page 18
- “Setting and Modifying Server Properties” on page 24
- “Implementing and Maintaining Your Licensing” on page 29
- “Upgrading from a Pre-Release 4.0 Release” on page 38

Note: If you are upgrading from a previous release, after you complete the steps in this chapter, you must follow the instructions for your product in “Upgrading from a Pre-Release 4.0 Release” on page 45.

Creating a Logon Account on Windows 2000 Server

To configure the ACR/Summary and ACR/Detail Server on Windows 2000, begin by creating a new user logon account for the server.

You do not have to create a logon account in the following situations:

- You are upgrading to a new release and have already created a user account.
- You already have an account that has the appropriate level of administrative privileges and access to other network directories.

To create the account, do the following:

1. Go to the Control Panel to select the Local Users and Groups option.
From the **Start** menu, choose **Settings > Control Panel > Administrative Tools > Computer Management** and select **Local Users and Groups**.

3 ■ Configuring and Licensing the Server

Creating a Logon Account on Windows 2000 Server

Note: If you are not in classic view, the navigation will be: **Start menu > Control Panel > Performance and Maintenance > Administrative Tools > Computer Management** and select **Local Users and Groups**.

- a. Highlight **Users**.
- b. Click **Action** on the menu bar and select **New User**.

A New User dialog box displays.

An alternative way to access the New User dialog box is:

From the **Start** menu, choose **Settings > Control Panel** and select **Users and Passwords**.

- a. From the Local Users and Passwords dialog box, click the **Advanced** tab.
 - b. Click the **Advanced** button to display the New User dialog box.
 - c. Highlight **Users**.
 - d. Click **Action** on the menu bar and select **New User**.
2. Complete the New User dialog box.

The screenshot shows the 'New User' dialog box with the following fields and options:


- User name: Infogix ACR Server
- Full name: ACR/Summary and ACR/Detail Service Account
- Description: Provides network services to sumdetsv.exe
- Password: [Redacted]
- Confirm password: [Redacted]
- User must change password at next logon
- User cannot change password
- Password never expires
- Account is disabled
- Buttons: Create, Close

- a. Enter the **User name**, **Full name**, and **Description** fields. You can copy the names and description shown New User dialog box sample above or use your own.
- b. Enter a **Password**.

Note: If input files for ACR/Summary or ACR/Detail jobs reside elsewhere on your network, make sure the username and password you specify are authorized to access the directories where those files reside.

- c. Disable the **User Must Change Password at Next Logon** option.
 - d. Enable the **Password Never Expires** option.
3. Click **Create**.
 4. Click **Close**.
 5. In the right frame of the Local Users and Groups window, select the user name you just created.


The properties dialog box for the ACR/Summary and ACR/Detail Server (or whatever name you specified for the server account) displays the **General** tab.




3 ■ Configuring and Licensing the Server

Creating a Logon Account on Windows 2000 Server

6. Click the **Member Of** tab.



7. Click **Add**.
8. When the Select Groups window appears, select **Administrators** and click **Add**. If appropriate, you can also make the account a member of additional groups.



9. Click **OK** to accept. Then, click **OK**, again, to create the account.

Start the Service on Windows 2000 Server

1. Select **Start > Settings > Control Panel > Administrative Tools > Services > ACR SumDet Server x.x.**
where x.x represents the release number. Including the release number in the service name allows you to install multiple releases on the same machine.
2. Click the **Log On** tab.
 - a. Select **This account.**
 - b. Browse for the ACR/Summary and ACR/Detail account you created on [page 15](#). If you did not create a new user account, browse for an account that has the appropriate level of administrative privileges and access to other network directories.
 - c. Once you select the account, type in the account's **Password**. You need to do this, even though the asterisks in the Password field make it look like a password has already been entered.
3. On the **General** tab, change the Startup type to **Automatic** if you want the ACR/Summary and ACR/Detail Server to automatically start up each time you reboot. Otherwise, whenever you reboot, you will have to start the server from the Services dialog box.

Note: The folder names for the path listed in **Path to executable** are truncated to eight characters. The full name of this path is:

C:\Infogix\SumDetServer\sumdetsv.exe

4. Click **Start**. The server's status will change to Started.
5. When you click **OK** and close the dialog box, the ACR/Summary and ACR/Detail Server is now ready to process requests from an ACR/Summary client or the ACR/Detail client. Review the information on "[Setting and Modifying Server Properties](#)" on [page 24](#) to verify the default settings or establish settings for e-mail notification or an ACR/Connector configuration.

3 ■ Configuring and Licensing the Server

Creating a Logon Account on Windows Server 2003 or XP

Creating a Logon Account on Windows Server 2003 or XP

To configure the ACR/Summary and ACR/Detail Server on a Windows Server 2003 or on Windows XP, begin by creating a new user logon account for the server.

You do not have to create a logon account in the following situations:

- You are upgrading to a new release and have already created a user account.
- You already have an account that has the appropriate level of administrative privileges and access to other network directories.

1. Select **Start > Control Panel > Administrative Tools > Computer Management > Local Users and Groups**
2. Highlight **Users** and click **Action > New User**.
3. Complete the New User dialog box.

The screenshot shows the 'New User' dialog box with the following fields and options:


- User name: Infogix ACR Server
- Full name: ACR/Summary and ACR/Detail Service Account
- Description: Provides network services to sumdetsv.exe
- Password: [Redacted]
- Confirm password: [Redacted]
- User must change password at next logon
- User cannot change password
- Password never expires
- Account is disabled
- Buttons: Create, Close

- a. Enter the **User name**, **Full name**, and **Description** fields. You can copy the names and description shown in the New User dialog box sample or use your own.
- b. Enter a **Password**.

Note: If input sources for ACR/Summary or ACR/Detail reside elsewhere on your network, make sure the username and password you specify are authorized to access the directories where those files reside.

- c. Disable the **User Must Change Password at Next Logon** option.
 - d. Enable the **Password Never Expires** option.
4. Click **Create > Close**.
 5. In the right frame of the Local Users and Groups window, select the user name you just created.


In the properties dialog box for the ACR/Summary and ACR/Detail Server (or whatever user name you specified for the server account), click the **Member Of** tab and click **Add**.




6. In the Select Groups window, enter **Administrators** in the object names text box.

3 ■ Configuring and Licensing the Server

Creating a Logon Account on Windows Server 2003 or XP




7. Click the **Check Names** button to display the full object name.



8. Click **OK** to add the group and click **OK** again to create the account. The Member Of tab shows that the ACR/Summary and ACR/Detail Server is a member of the Administrators and Users groups. If appropriate, you can also make the account a member of additional groups.

Start the Service on Windows Server 2003 or XP


1. Select **Start > Settings > Control Panel > Administrative Tools > Services > ACR SumDet Server x.x.**
 where x.x represents the release number. Including the release number in the service name allows you to install multiple releases on the same machine.
2. Click the **Log On** tab. For **Log on as**, select **This account**, as shown below.




3 ■ Configuring and Licensing the Server

Creating a Logon Account on Windows Server 2003 or XP

3. Click **Browse** to open the Select User dialog box.



4. Enter the User name that you entered on [page 18](#) for the ACR/Summary and ACR/Detail Server account. On [page 18](#), the user name was Infogix ACR Server, although you may have specified a different name. If you did not create a new user account, enter an account name that has the appropriate level of administrative privileges and access to other network directories.
5. Click the **Check Names** button to display the full account name, and click **OK** to close this dialog box and return to the previous one.



6. In the Log On tab of the ACR/Summary and ACR/Detail Server Properties dialog box, enter the account's **Password**. You need to do this even though the asterisks in the Password field make it look like a password has already been entered.
7. Click **Apply**.
8. In the **General** tab on the ACR/Summary and ACR/Detail Server Properties dialog box, change the Startup type to **Automatic** if you want the ACR/Summary and ACR/Detail Server to automatically start up each time you reboot. Otherwise, whenever you reboot, you will have to start the server from the Services dialog box.

Note: The folder names for the path listed in **Path to executable** are truncated to eight characters. The full name of this path is:

C:\Infogix\SumDetServer\sumdetsv.exe


9. Click **Start > OK**. The ACR/Summary and ACR/Detail Server is now ready to process requests from an ACR/Summary client or the ACR/Detail client. Review the information on "[Setting and Modifying Server Properties](#)" on page 24 to verify the default settings or establish settings for e-mail notification or an ACR/Connector configuration.

Setting and Modifying Server Properties

Once you have created a logon account, you can set up and modify properties of the ACR/Summary and ACR/Detail Server in the Server Properties dialog box. Properties include communications, e-mail notification, message logging, and runtime options, as well as the licensing Control File. Some of these properties are set during installation of the server, while others can only be specified in the Server Properties dialog box. For example, if you want to select an ACR/Connector configuration or activate the e-mail notification feature, you must specify the appropriate settings in the properties dialog box. To display the ACR/Summary and ACR/Detail Server Properties dialog box, select the ACR SumDet Server 4.1 icon on the Control Panel. The upcoming sections describe the properties on each tab.

Communications


The Communications tab shows port number settings and optional ACR/Connector configuration selection.



The **User port number** and **Administration port number** display the Communication Parameters established during installation, as described in [step 5 on page 9](#). The above example shows the default port

numbers which are generally the ones used. If it is necessary to change the port numbers due to a conflict with some other software, click **Help** for details.

If your ACR/Summary or ACR/Detail installation includes ACR/Connector, select the configuration name to enable. Do not select an ACR/Connector configuration unless you want to activate ACR/Connector for all jobs running on the server.



Keep in mind that the ACR/Connector IN/Sync feature lets ACR/Connector launch other applications on other platforms (such as the mainframe) depending on the outcome of specific ACR/Summary or ACR/Detail jobs. This is desirable when jobs are running in production on the ACR/Summary and ACR/Detail Server. For example, suppose your organization has a system that can issue pager messages. You might have IN/Sync tell the paging system to send a pager message whenever a particular job issues a return code corresponding to a specified out-of-balance condition.

When users are setting up and testing ACR/Summary or ACR/Detail jobs, they probably won't want IN/Sync to launch other applications based on the jobs' outcomes. In the example above, it would be annoying for a supervisor to receive a pager message each time a test job was out

3 ■ Configuring and Licensing the Server


Setting and Modifying Server Properties

of balance. This could happen if IN/Sync was set up to trigger a pager message for a production job that had the same name and issued the same return code as a test job.

If you are using ACR/Connector, the best way to avoid unexpected results may be to set up two ACR/Summary and ACR/Detail Server installations—one for testing and one for production. Then, implement the IN/Sync feature on the production server, but not on the test server. Users can switch from testing to production by running their jobs on the appropriate server. For more information, see the *ACR/Connector Installation and User Guide*.


Message Logging

The Message Logging tab displays the Log File Options established during installation, as described in [step 7 on page 10](#). Messages are automatically deleted from the log after the set number of days. The **Purge now** button enables you to delete all the log entries at any time. Click **Help** for details.



E-mail Notification

To activate the ACR/Summary and ACR/Detail e-mail notification feature, specify the host name/address and port number of your SMTP Internet mail server. Click **Help** for details.



For **SMTP host name/address**, enter the host name or IP address of your Internet mail server. For **SMTP port number**, accept 25 unless your mail server has a different port number.


Once you specify this information, ACR/Summary and ACR/Detail jobs that run on the server will be able to issue e-mail messages when they are out of balance. The user specifies the message to send and the e-mail address where the message should be sent. The message and e-mail address are specified in the Messages dialog box of ACR/Detail or the Direct Messages dialog box of ACR/Summary.

3 ■ Configuring and Licensing the Server

Setting and Modifying Server Properties


Runtime Options

The Runtime Options tab should keep the default setting of **+S5-NO** for the **Run-time switch**. Do not change this setting unless told to do so by Customer Support.



Control File

The Control File tab is documented in the following section on [Implementing and Maintaining Your Licensing](#). Use the Control File tab to activate or update your product license.



Implementing and Maintaining Your Licensing

The ACR/Summary and ACR/Detail Server includes a Control File that enables and controls access to your product in accordance with your license agreement. This section shows you how to do the following:

- Update your Control File.
- Generate the TM Aggregate Transaction Report, if requested.

Updating a Control File

There are several situations when you need to perform this update. The most common include:

- When you install the ACR/Summary and ACR/Detail Server for the first time.
- When the terms of your license have changed.
- When your license for ACR/Summary and ACR/Detail is about to expire, as indicated by warning or error messages in your SYSOUT.

3 ■ Configuring and Licensing the Server

Implementing and Maintaining Your Licensing

- When you want to run the product(s) on a machine with a host name that is not currently included in your license.

Generating the Licensing Report(s)

To generate the Product Report (file name UNI10PR.RPT), install and open the ACR/Summary and ACR/Detail Server and select the Control File tab from the server properties dialog box.

1. Complete the **Control File** field with the fully qualified name of the Control File specified during installation. To browse for the Control File (acrcntl.dat), click the button next to the field.

For example, if you accepted the default location during installation, the fully qualified name is:

`C:\Infogix\SumDetServer\Cobol\acrcntl.dat`

2. Select **Control File Utilities**.
3. Click **Print**.

The following report(s) will display in a new window:

- The Product Report (UNI10PR.RPT) displays the current licensing information from the Control File.
- If the Control File has ever included Transactional Measurement (TM) licensing, a Transactional Measurement Report (UNI10PRA.RPT) will be generated.

Note: If the TM column in the Product Report has the value of N (No), the TM licensing shown in the Transactional Measurement Report for that product is not currently in effect.

4. Click **Print** to print the report(s).

Following are examples of each report.

Product Report (UNI10PR.RPT)

releasenumbr	PRODUCT REPORT	COPYRIGHT	INFOGIX, INC.					
DATE: 03042		PAGE:	1					
TIME: 13:21		REPORT:	UNI10PR					
FILENAME: "C:\Infogix\SumDetServer\Cobol\Acrcntl.dat"								
CUSTOMER: INFOGIX, INCORPORATED								
PAGE:060 WAIT:0900 RES:Y I-RET:0000 W-RET:0000 E-RET:4000 UPDATE:004								
PRODUCT	EXP	GRACE	AUTH	TYPE	TM	HOSTNAME	MODEL	ID
U/SUM	99/999	7	ALL	H	N	001234X86X		
						333334444		
						555556666		
						777778888		
						999990000		
						222224444		
						222221111		
VIOLATION:	FIRST DATE	LAST DATE		HOSTNAME		TYPE		
	00/000	00/000				HARDWARE		
	00/000	00/000				HARDWARE		
	00/000	00/000				HARDWARE		
	00/000	00/000				HARDWARE		

3 ■ Configuring and Licensing the Server

Implementing and Maintaining Your Licensing

Transactional Measurement Report (UNI10PRA.RPT)

```
releasenumber  TRANSACTIONAL MEASUREMENT REPORT  COPYRIGHT INFOGIX, INC.
DATE: mm/dd/yy                PAGE:                01
TIME: 15:20                   REPORT:         UNI10PRA

CUSTOMER:      Infogix, INCORPORATED
PAGE:060  WAIT:0900  RES:Y  I-RET:0000  W-RET:0000  E-RET:4000  UPDATE:002

-----LICENSE-----
PRODUCT TM  IND      VALUE      GRACE      RESET      VALUE
U/SUM  RULD EXEC      5,000      40      03/135      5,060
-----VIOLATION PER LICENSE INTERVAL-----
FIRST  LAST      VALUE      COUNT
03/135 03/135      5,050      3
-----VIOLATION PER CHANGE OF LICENSE VALUE-----
FIRST  LAST      MAXIMUM VALUE      TOTAL
03/010 03/135      5,100      50

-----LICENSE-----
PRODUCT TM  IND      VALUE      GRACE      RESET      VALUE
U/SUM  RULM EXEC      150,000      40      03/130      10,000
-----VIOLATION PER LICENSE INTERVAL-----
FIRST  LAST      VALUE      COUNT
00/000 00/000      0      0
-----VIOLATION PER CHANGE OF LICENSE VALUE-----
FIRST  LAST      MAXIMUM VALUE      TOTAL
00/000 00/000      0      0

-----LICENSE-----
PRODUCT TM  IND      VALUE      GRACE      RESET      VALUE
U/SUM  RECD EXEC      100(IN 000S)      20      03/135      90,000
-----VIOLATION PER LICENSE INTERVAL-----
FIRST  LAST      VALUE      COUNT
00/000 00/000      0      0
-----VIOLATION PER CHANGE OF LICENSE VALUE-----
FIRST  LAST      MAXIMUM VALUE      TOTAL
00/000 00/000      0      0

(Actual report may show information for additional TM types
and additional products.)
```

5. Request your control cards and password.


Using the information in “[Contacting Customer Support](#)” on page 6, do the following:

- a. Call Customer Support to advise that you are updating the Control File according to your license agreement. Be ready to provide the reason for the update and the scheduled date.
- b. E-mail or fax the report(s) generated in the previous step to Customer Support. Mention any special considerations. For example, inform Customer Support if you are upgrading to a new release or upgrading a CPU. You will receive an e-mail or fax containing your control cards and password.

Performing the Update

After receiving the fax or e-mail containing the control card(s) and password, complete the following steps:


1. Open the ACR/Summary and ACR/Detail Server and select the Control File tab, shown below.



2. In the **Control File** field, enter the fully qualified name of the Control File you are updating. The full name of the path shown above for the Control File is:
C:\Infogix\SumDetServer\Cobol\ACRCNTL.DAT
3. Click **Update**. The Update Control File dialog box displays an empty Control Cards text box.
4. Type or paste the control cards and password from the fax or e-mail into the Control Cards area. Below is an example completed control card information:

3 ■ Configuring and Licensing the Server

Implementing and Maintaining Your Licensing



5. Click **OK**.

The Control File Update (UNIFAX50.RPT) report will be displayed in a new window. Click **Print** if you want to print the report.

Following is an example of the report.

```
CHANGE ID: 11111222202351003
UNICF:  UNI.REL33.UNICF
ACCEPTED  USUM3 CT 7761  C
ACCEPTED  USUM3CCL 6805 AAAAAAAAA MF3000L2 0000 0308
ACCEPTED  USUM3CCA 2836 A S
ACCEPTED  USUM3CCE 7600 03150 04150
ACCEPTED  USUM3CCG 8666 03 30
ACCEPTED  PW 6947 JQQJQQJQQJ 673720
*****REQUEST PHASE COMPLETE*****
CHANGED  USUM3 CT 1677  C
CHANGED  USUM3CCL 5086 AAAAAAAAA MF3000L2 0000 0308
CHANGED  USUM3CCA 6382 A S
CHANGED  USUM3CCE 0067 03150 04150
CHANGED  USUM3CCG 6668 03 30
UPDATE COMPLETE
```

6. Verify the update by reviewing the UNIFAX50.RPT. If the update completed successfully, the report should contain the message **UPDATE COMPLETE**. If the report shows that any of the control cards failed, print and fax or e-mail the report to Customer Support for assistance.

Generating the TM Aggregate Transaction Report


The TM Aggregate Transaction Report is an encrypted report that you may be requested to run by a member of the Customer Development and/or Market Development team. The report prints aggregate counts for each transaction type that is being tracked. Transaction types can include jobs, input sources, records, and rules. After you e-mail the report to the requestor at Infogix, it is decrypted and used for the following purposes:

- To aid in analyzing your transaction usage.
- To implement actual transaction usage licensing where you are billed on a “pay as you go” basis.

Follow the steps below to generate the report from the Control File.

1. Open the ACR/Summary and ACR/Detail Server and select the **Aggregate Transaction Report Utilities** button on the Control File tab.
2. Click **Print** or **Print and Reset**, depending on whether or not you want to reset the transaction counts. In either case, the Print Aggregate Transaction Report dialog box appears.

The Control Cards text box is blank until you enter one of the options described in the next steps.



3 ■ Configuring and Licensing the Server

Implementing and Maintaining Your Licensing

3. If you selected **Print**, enter one of the following options in the Control Cards text box. Otherwise skip to step 4. (Entries should be made on the first line only, starting at the left end of the line.)

Option	Purpose
ALL P	Print the aggregate counts for both ACR/Summary and ACR/Detail. (Leave one space between ALL and P .)
USUMP	Print the aggregate counts for ACR/Summary only.
UDRSP	Print the aggregate counts for ACR/Detail only.

4. If you selected **Print and Reset**, enter one of the following options in the Control Cards text box. Entries should be made on the first line only, starting at the left end of the line.

Option	Purpose
ALL R	Print the aggregate counts and reset the counters for both ACR/Summary and ACR/Detail. (Leave one space between ALL and R .)
USUMR	Print the aggregate counts and reset the counters for ACR/Summary only.
UDRSR	Print the aggregate counts and reset the counters for ACR/Detail only.

5. When you click **OK**, the aggregate report displays in a new window. The report name is UNITMPRT.RPT for the print version and UNITMRST.RPT for the print and reset version.
If you examine the report file, the contents will be encrypted as in the following example:

```
1C:\Infogix\ACRServer\          Infogix, INCORPORATED
02CFLNFGHIJABCDEFGHIJABDDEFGHIJABCDEFGHIJBBCEFGHIJABCDEFGHIJABCDEFHJMABCDEFGHIJABCDEFHH
02FKMEFGHIJABCDEFGHIJABCDEFGHIJABCDEFGHIJABCDEFGHIJABCDEFGHIJABCDEFGHIJABCDEFGHIJABCDEFGHIJ
```

6. If you are going to fax the report to the requestor at Infogix, click **Print** to print the report.
7. Fax or e-mail the report to the person who requested it.

More About the Entry Format for the Aggregate Transaction Report Dialog Box

The information in the preceding section provides all you need to generate a Transaction Measurement (TM) Report. The following information provides additional detail about the Print Aggregate Transaction Report dialog box that displays when you select Aggregate Transaction Management Utilities option on the Control File tab of the Server Properties dialog box. This information will be helpful if you expand TM licensing to additional products in the future.

Although the Print Aggregate Transaction Report dialog box initially displays blank, it requires information to be in the format described below. Information should only be entered on the first line.

The following graphic shows the left end of the dialog box.

1	2	3	4	5
12345678901	2345678901	2345678901	2345678901	234567890
PPPP	PPPP	PPPP	PPPP	PPPP

PPPPO is repeated 16 times on the line. (The entire line is not shown here.) To allow TM licensing for additional products in the future, a total of 16 products can be specified using the **PPPPO** format.

The first four characters in the positions **PPPP** at the left end of the line specify the product name. Valid entries are as follows:

- **ALL** (followed by a space to extend the entry to four characters) indicates that aggregate counts will be included for each product in the Control File for which TM aggregate counts exist.
- **USUM** indicates that aggregate counts will be included for ACR/Summary only.
- **UDRS** indicates that aggregate counts will be included for ACR/Detail only.

Note: The product name must match the information in the your Control File.

The fifth character is entered in the position **O** at the left end of the line and is used to specify the process option, as follows:

- **P** specifies the Print Only option.
- **R** specifies the Print and Reset option.

Upgrading from a Pre-Release 4.0 Release

If you are upgrading from a pre-Release 4.0 release, go to [“Upgrading from a Pre-Release 4.0 Release”](#) on page 45.

Installing a Client

This chapter provides the system requirements and instructions for installing ACR/Summary Client or ACR/Detail Client. It contains the following sections:

- [Before You Begin](#) - page 39
- [System Requirements for a Client](#) - page 39
- [Steps for Installing a Client](#) - page 40

Before You Begin

Before you begin installation, do the following:

- Verify that the system where you plan to install the client meets the requirements described in “[System Requirements for a Client](#)” on [page 39](#).
- Arrange for network access to ACR/Summary and ACR/Detail Server.

System Requirements for a Client

Category	Requirement
Hardware and Operating System	IBM or compatible machine with Microsoft Windows 2000, Windows XP, or Windows Vista
Memory	At least 64 MB of Random Access Memory (RAM)
Disk Space	A hard drive with at least 10 MB of free space
Drive	CD-ROM
Network Communication	Access to a network using TCP/IP protocol

System requirements for the ACR/Summary and ACR/Detail Server are on [page 7](#).

Steps for Installing a Client

1. From the PC where you will install the client, select the appropriate setup program on the ACR/Summary and ACR/Detail x.x Server (where x.x represents the release number):
 - **SetupSum.exe** for ACR/Summary Client
 - **SetupDet.exe** for ACR/Detail ClientThe program is normally in the server's Infogix\SumDetServer\Client directory.
2. The installation wizard will prompt you through the process. When the process completes, the ACR/Summary Client or the ACR/Detail Client will be installed in the Infogix program group, unless you specified a different installation directory.
3. If you have both clients, repeat the installation process for the remaining product.

Following installation, see the appropriate user guide for instructions on accessing, configuring and using the clients:

- *ACR/Summary User Guide for Windows and UNIX*
- *ACR/Detail User Guide for Windows and UNIX*

Installing and Licensing ACR/Workbench

If you purchased the ACR/Workbench for Summary or ACR/Workbench for Detail, this chapter provides the installation and licensing instructions.

This chapter contains the following sections:

- “System Requirements for ACR/Workbench” on page 41
- “Overview of ACR/Workbench Installation and Setup Steps” on page 42
- “Uninstall the Previous Release if Appropriate” on page 42
- “Installing the CD” on page 42
- “Installing the Net Express Licensing Key” on page 43
- “Upgrading from a Pre-Release 4.0 Release” on page 44
- “Using ACR/Workbench” on page 44

System Requirements for ACR/Workbench

Below are the minimum system requirements for the ACR/Workbench for Summary or ACR/Workbench for Detail:

Category	Requirement
Hardware and Operating System	IBM or compatible machine with Microsoft Windows 2000, Windows XP, or Windows Vista
Processor	Intel Pentium III or Pentium IV, or equivalent
Memory	At least 64 MB of Random Access Memory (RAM)
Disk Space	A hard drive with at least 30 MB of free space (more if data files are stored locally)
Drive	CD-ROM

Overview of ACR/Workbench Installation and Setup Steps

This section summarizes the steps for installation and setup of the ACR/Summary and ACR/Detail Server and Client(s). Consult the next sections in order to perform the steps.

Uninstall the Previous Release if Appropriate

If you are upgrading from a previous release, uninstall the old release only if appropriate, as explained below:

- If you want to install and test the new release of ACR/Workbench while continuing to support the old release (this is called a dual install), do not uninstall the old release.
- If you do not want to use the dual install feature, uninstall the previous version of ACR/Workbench using the **Add or Remove Programs** option on the Control Panel.

Installing the CD

Note: Before you begin, review “[Uninstall the Previous Release if Appropriate](#)” above. Ensure that you have uninstalled the previous release only if you do not want to use dual install.

1. Insert the installation CD into the CD-ROM drive on the PC.
2. The installation program usually starts automatically. If it does not, select **R**un from the Start menu and run the **setup.exe** program located on the CD.
3. Follow the prompts through the installation process.

The program will install the product in the one of the following unless you specify a different installation directory:

C:\Infogix\Detail32
C:\Infogix\Summary32

Installing the Net Express Licensing Key

When you install ACR/Workbench for the first time, a Micro Focus licensing key is required to properly run ACR/Summary or ACR/Detail jobs. If you install both products, you only need to install the key once. Instructions for installing the key are provided below.

1. Use Windows Explorer to display the contents of the installation folder that was created in [step 3 on page 42](#). Open the appserv (Application Server) subfolder.
2. Select **setup.exe** to launch the Micro Focus Application Server for Net Express 4.0 Setup wizard.

If you need to install the licensing key, the setup program wizard will prompt you through the process, as described in the next step. If you already have the proper licensing key installed, the message APPLICATION SERVER FOR NET EXPRESS 4.0 IS ALREADY INSTALLED displays. Click **No** at the upgrade option and **OK** at the second message that displays.

3. To proceed with the licensing setup, follow the instructions on the screen and accept the default settings.

Note: We recommend that you accept the default location for the licensing files. The licensing files cannot be in the same location as the ACR/Workbench DLLs.

4. Call Customer Support when you reach the License Registration dialog box. See [“Contacting Customer Support” on page 6](#). A representative will give you a serial number and a license number to enter in the dialog box.
5. Once you have entered the numbers, click **OK**. Then, click Next until the LICENSE INSTALLED OK message displays. Click **OK**, again. Then, click Next until the message SETUP COMPLETED SUCCESSFULLY displays.
6. If you purchased both ACR/Workbench for Summary and ACR/Workbench for Detail, repeat the instructions in [“Installing the CD” on page 42](#). You do not need to repeat the instructions in this section as you only need to install one Net Express key on each PC where the ACR/Workbench is installed.

Upgrading from a Pre-Release 4.0 Release

See the instructions in “Upgrading from a Pre-Release 4.0 Release” on page 45.

Using ACR/Workbench

Refer to one of the following guides for instructions on starting, configuring, and using ACR/Workbench.

- “Using the Workbench” appendix in *ACR/Summary User Guide for Windows and UNIX*.
- “Using the Workbench” appendix in *ACR/Detail User Guide for Windows and UNIX*.

Upgrading from a Pre-Release 4.0 Release

This chapter provides instructions for upgrading ACR/Summary and ACR/Detail Server and ACR/Workbench from a release previous to Release 4.0.

Release 4.0 provides extended internal items, which increase the maximum extractible length for numeric data from 15 to 30 digits, and for text data from 8 to 80 characters. The upgrade procedures described here expand your definition and history databases to make room for these new items.

ACR/Summary and ACR/Detail each have two expansion utilities for this purpose: one for expanding the history database and another for expanding the definition database. The utilities and sample batch files for running them are included with Release 4.1 of ACR/Summary and ACR/Detail Server and ACR/Workbench.

To run the expansion utilities under Windows, you need to know how to edit and execute batch files.

Note: These upgrade procedures should be followed after you have installed the new release and updated your license based on the instructions in the preceding chapters.

This document contains the following sections:

- “Upgrading ACR/Summary for Windows” on page 45
- “Upgrading ACR/Detail for Windows” on page 49

Upgrading ACR/Summary for Windows

Expanding the History Database for ACR/Summary

The ACR/Summary History Expansion Utility (SUMEXPHF.BAT) copies and expands pre-release 4.0 history data into a history database for Release 4.0 or higher.

This utility produces a System Output Report (SYSOUT.rpt) that lists any system output messages.

6 ■ Upgrading from a Pre-Release 4.0 Release

Upgrading ACR/Summary for Windows

The steps for editing and running SUMEXPHF.BAT are as follows:

1. Make a copy of the SUMEXPHF.BAT file for modification. Do not modify the original template.

Warning: It is very important that you perform the expansion on a copy of SUMEXPHF.BAT, and keep the original as a backup.

The .bat file will be in one of the following locations:

- If you have ACR Summary and ACR/Detail Server, SUMEXPHF.BAT is in the \bat folder. The default installation path for the Server is C:\Infogix\ACRSumDet Server.
 - If you have ACR/Workbench for Summary, SUMEXPHF.BAT is in the ACR/Summary installation directory. The default installation path is C:\Infogix\Summary32.
2. Open the copy you made of SUMEXPHF.BAT file and perform the following edits:

Warning: You MUST make these edits before running the .bat file.

- c. Edit the ACRSWB parameter, highlighted below:

```
::
-----
:: Set ACR/Summary working directory
::-----
SET ACRSWB=??????
```

Do one of the following:

- If you have the Server, replace ?????? with the path of the ACR COBOL directory.
 - If you have ACR/Workbench for Summary, replace ?????? with the ACR/Summary installation directory. The installation directory is the one that contains unirun.exe.
- d. In the default values section of the .bat file, shown below, define the following files that are input or output of the utility:

```
::-----
:: Set the default values for the files and parameters
::-----
SET UNIHFOLD=??????
SET UNIHF=??????
```

UNIHFOLD: Replace ?????? with the path and name of the pre-Release 4.0 ACR/Summary history database file that contains the history data you want to copy/expand.

UNIHF: Replace ?????? with the path and name of the new ACR/Summary history database file.

3. Save your changes and run SUMEXPHF.BAT.
4. Check the SYSOUT report for any error messages.

Expanding the Definition Database for ACR/Summary

The ACR/Summary Definition Expansion Utility (SUMEXPDEF.BAT) copies and expands pre-release 4.0 definition data into a definition database for Release 4.0 or higher.

This utility produces a System Output Report (SYSOUT.rpt) that lists any system output messages.

The steps for editing and running SUMEXPDEF.BAT are as follows:

1. Make a copy of the SUMEXPDEF.BAT file for modification. Do not modify the original template.

Warning: It is very important that you perform the expansion on a copy of SUMEXPDEF.BAT, and keep the original as a backup.

The .bat file will be in one of the following locations:

- If you have ACR Summary and ACR/Detail Server, SUMEXPDEF.BAT is in the \bat folder. The default installation path for the Server is C:\Infogix\ACRSumDet Server.
- If you have ACR/Workbench for Summary, SUMEXPDEF.BAT is in the ACR/Summary installation directory. The default installation path is C:\Infogix\Summary32.

6 ■ Upgrading from a Pre-Release 4.0 Release

Upgrading ACR/Summary for Windows

2. Open the copy you made of SUMEXP.DAT file and perform the following edits:

Warning: You MUST make these edits before running the .bat file.

- a. Edit the ACRSWB parameter, highlighted below:

```
::
```

```
-----  
:: Set ACR/Summary working directory  
::-----
```

```
SET ACRSWB=??????
```

Do one of the following:

- If you have the Server, replace ?????? with the path of the ACR COBOL directory.
 - If you have ACR/Workbench for Summary, replace ?????? with the ACR/Summary installation directory. The installation directory is the one that contains unirun.exe.
- b. In the default values section of the .bat file, shown below, define the following files that are input or output of the utility:

```
::-----  
:: Set the default values for the files and parameters  
::-----
```

```
SET UNIINP=UNIINP.DAT  
SET UNIDFOLD=??????  
SET UNIDF=??????
```

UNIDFOLD: Replace ?????? with the path and name of the pre-Release 4.0 ACR/Summary definition database file that contains the definition data you want to copy/expand.

UNIDF: Replace ?????? with the path and name of the new ACR/Summary definition database file.

3. Save your changes and run SUMEXP.DAT.
4. Check the SYSOUT report for any error messages.

Optional: Update Job Output Options

For existing (pre-release 4.0) jobs, the default for the Extended Internal Items option in the Job Output Options dialog box is Do not print. This means that the Extended Internal Items section will not be included in the Control Report for those jobs.

(For new jobs created after the upgrade to Release 4.0, the default for this option will be Print.)

If your site wants the Extended Internal Items section to print in the Control Report for one or more existing jobs that you plan to use after the upgrade, you need to make a change to the job output options for each of those jobs as follows:

1. Open ACR/Summary.
2. Open the job.
3. Select Print Control Reports.
4. Change the Extended Internal Items option to Print.

Upgrading ACR/Detail for Windows

Expanding the History Database for ACR/Detail

The ACR/Detail History Expansion Utility (DETEXPHF.BAT) copies and expands pre-release 4.0 history data into a history database for Release 4.0 or higher.

This utility produces a System Output Report (SYSOUT.rpt) that lists any system output messages.

The steps for editing and running DETEXPHF.BAT are as follows:

1. Make a copy of the DETEXPHF.BAT file for modification. Do not modify the original template.

Warning: It is very important that you perform the expansion on a copy of DETEXPHF.BAT, and keep the original as a backup.

The .bat file will be in one of the following locations:

- If you have ACR Summary and ACR/Detail Server, DETEXPHF.BAT is in the \bat folder. The default installation path for the Server is:
C:\Infogix\ACRSumDet Server.

6 ■ Upgrading from a Pre-Release 4.0 Release

Upgrading ACR/Detail for Windows

- If you have ACR/Workbench for Detail, DETEXPHF.BAT is in the ACR/Detail installation directory. The default installation path is C:\Infogix\Detail32.
2. Open the copy you made of DETEXPHF.BAT file and perform the following edits:

Warning: You MUST make these edits before running the .bat file.

- a. Edit the ACRDWB parameter, highlighted below:

```
::  
-----  
:: Set ACR/Detail working directory  
:-----  
SET ACRDWB=??????
```

Do one of the following:

- If you have the Server, replace ?????? with the path of the ACR COBOL directory.
 - If you have ACR/Workbench for Detail, replace ?????? with the ACR/Detail installation directory. The installation directory is the one that contains unirun.exe.
- b. In the default values section of the .bat file, shown below, define the following files that are input or output of the utility:

```
::-----  
:: Set the default values for the files and parameters  
:-----  
SET UNIHFOLD=??????  
SET UNIHF=??????
```

UNIHFOLD: Replace ?????? with the path and name of the pre-Release 4.0 ACR/Detail history database file that contains the history data you want to copy/expand.

UNIHF: Replace ?????? with the path and name of the new ACR/Detail history database file.

3. Save your changes and run DETEXPHF.BAT.
4. Check the SYSOUT report for any error messages.

Expanding the Definition Database for ACR/Detail

The ACR/Detail Definition Expansion Utility (DETEXPDF.BAT) copies and expands pre-release 4.0 definition data into a definition database for Release 4.0 or higher.

This utility produces a System Output Report (SYSOUT.rpt) that lists any system output messages.

The steps for editing and running DETEXPDF.BAT are as follows:

1. Make a copy of the DETEXPDF.BAT file for modification. Do not modify the original template.

Warning: It is very important that you perform the expansion on a copy of DETEXPDF.BAT, and keep the original as a backup.

The .bat file will be in one of the following locations:

- If you have ACR Summary and ACR/Detail Server, DETEXPDF.BAT is in the \bat folder. The default installation path for the Server is C:\Infogix\ACRSumDet Server.
 - If you have ACR/Workbench for Detail, DETEXPDF.BAT is in the ACR/Detail installation directory. The default installation path is C:\Infogix\Detail32.
2. Open the copy you made of DETEXPDF.BAT file and perform the following edits:

Warning: You MUST make these edits before running the .bat file.

- a. Edit the ACRDWB parameter, highlighted below:

```

::
-----
:: Set ACR/Detail working directory
::-----
SET ACRDWB=??????
    
```

Do one of the following:

- If you have the Server, replace ?????? with the path of the ACR COBOL directory.
 - If you have ACR/Workbench for Detail, replace ?????? with the ACR/Detail installation directory. The installation directory is the one that contains unirun.exe.
- b. In the default values section of the .bat file, shown below, define the following files that are input or output of the utility:

6 ■ Upgrading from a Pre-Release 4.0 Release

Upgrading ACR/Detail for Windows

```
:-----  
:: Set the default values for the files and parameters  
:-----  
  
SET UNIINP=UNIINP.DAT  
SET UNIDFOLD=??????  
SET UNIDF=??????
```

UNIDFOLD: Replace ?????? with the path and name of the pre-Release 4.0 ACR/Detail definition database file that contains the definition data you want to copy/expand.

UNIDF: Replace ?????? with the path and name of the new ACR/Detail definition database file.

3. Save your changes and run DETEXPDF.BAT.
4. Check the SYSOUT report for any error messages.

Index

A

- ACR/Connector
 - configuring communications for **25**
 - IN/Sync feature **25**
- ACR/Workbench
 - dual install **42**
 - installing **41**
 - installing the CD **42**
 - requirements **41**
- ACRCNTL.DAT (Control File) **33**
- administering the server
 - on Windows 2000 **13**
 - on Windows 2003 **18**
- Administration port number **9, 24**
- Aggregate Transaction Report
 - entry format **37**
 - generating **35**
 - sample **36**
 - see Transaction Measurement Report

C

- CD
 - for installing the server **9**
- client
 - installing **40**
 - system requirements **39**
 - User port number **10, 25**
- communications
 - activating e-mail notification **27**
 - Administration port number **9, 24**
 - for ACR/Connector **25**
 - User port number **10, 24**
- configuring the server **13**
- contacting Product Support
 - for licensing upgrades **32**
- Control File
 - ACRCNTL.DAT **33**
 - aggregate count print and reset options **36**
 - aggregate count print options **36**
 - completion report **34**

- contacting Product Support **32**
 - licensing **29**
 - tab in server properties dialog box **29**
 - updating **33**
 - when to update **29**
- Control File Update report **34**
 - Control Panel
 - accessing on Windows 2000 Server **13**

D

- dual install
 - ACR/Workbench **42**
 - server **8**

E

- e-mail notification (server properties) **27**

I

- IN/Sync **25**
- installation
 - of client **39, 40**
 - of Net Express key
 - for ACR/Workbench **43**
 - for server **11**
 - of server **7**
- installing ACR/Workbench **42**

K

- key for Net Express **11**

L

- licensing **13**
 - Control File **29**
 - generating TM Report **34**
 - Micro Focus Application Server
 - key for Net Express **11**
 - reports **30**
 - UNIFAX50.RPT **34**
- updating the Control File
 - performing the update **33**
 - preparation **29**
- log **10**

logon account for server
on Windows 2000 **13**
on Windows 2003 **18**

M

Member Of
server properties (Windows 2000) **16**
server properties (Windows 2003) **19**
message logging
setting during installation **10**
setting through server properties **26**
Micro Focus Application Server
licensing key **11**

N

Net Express licensing key **11**
notification by e-mail **27**

O

operating system
requirement for ACR/Workbench **41**

P

ports
for client users **9, 24**
for server administration **9, 24**
Product Report (UNI10PR.RPT) **30**
Product Support
contacting for Control File updates **32**

R

reports
Aggregate TM count (UNITMPRT.RPT)
36
Aggregate TM count and reset
(UNITMRST.RPT) **36**
Control File Update Report
(UNIFAX50.RPT) **33, 34**
for licensing control **30**
Product Report (UNI10PR.RPT) **30**
Transaction Management Report
(UNI10PRA.RPT) **31**
reset Aggregate TM counts (Control File)
36
runtime options (server properties) **28**

S

server
Control File **29**
creating logon account
on Windows 2000 **13**
on Windows 2003 **18**
dual install **8**
installing **8, 9**
log **10**
starting on Windows 2000 **17**
starting on Windows 2003 or XP **21**
system requirements **7**
server properties
Communications **24**
configuring or modifying **24**
Control File **29**
Email notification **27**
General (Windows 2000) **16**
Member Of (Windows 2000) **16**
Member Of (Windows 2003) **19**
Message logging **26**
Runtime options **28**
setup.exe **42**
for server **9**
for server Net Express key **11**
SetupDet.exe **40**
SetupSum.exe **40**
starting the ACR server
on Windows 2000 **17**
on Windows 2003 or XP **21**
support
contact information **6**
system requirements
ACR/Workbench **41**
clients **39**
server **7**

T

technical support
contact information **6**
TM
aggregate counts
for ACR/Detail, only **37**
for ACR/Summary, only **37**
for all **37**
Aggregate report

- count **35**
- count and reset **35**
- entry format for Aggregate Transactions **37**
- field for TM in Product Report **30**
- Transaction Measurement (TM) Report
 - generating **30**
 - sample (UNILSTA) **31**
 - see Aggregate Transaction Report
- transaction reports
 - aggregate **35**
 - generated with Control File Utilities **30**

U

- UNI10PR.RPT (Product Report) **30**
- UNI10PRA.RPT (Transaction Management Report) **30**
- UNIFAX50.RPT (Control Update) **34**
- UNILSTA (TM Report) **31**
- UNITMPRT.RPT (Aggregate TM count) **35, 36**
- UNITMRST.RPT (Aggregate TM count and reset) **35, 36**
- updating or modifying
 - server properties **24**
- updating the Control File
 - performing the update **33**
 - preparation **29**
- user port number **10, 24**

W

- Windows
 - requirements for ACR/Workbench **41**
- Write messages to log file **10**

