



# ACR/Summary<sup>®</sup> and ACR/Detail<sup>®</sup>

## Installation Guide for UNIX<sup>®</sup> and Linux<sup>®</sup> | ACR 4.9



Home Office

1240 East Diehl Road, Suite 400

Naperville, IL 60563

Tel: + 1.630.505.1800

[www.infogix.com](http://www.infogix.com)



Infogix, the Infogix checkmark logo, Infogix Assure, Infogix Insight, ACR, ACR/Detail, ACR/Summary, ACR/Workbench, ACR/Connector, ACR/Instream, ACR/File, Infogix ER, Infogix DTM, Infogix Perceive, Infogix Nexix, Information Integrity, and Information With Confidence are registered trademarks of Infogix, Inc.

Infogix Controls and The Information Integrity Experts are trademarks of Infogix, Inc.

Any other trademarks or registered trademarks are the property of their respective owners.

Copyright 1998–2016 Infogix, Inc. All rights reserved.

Confidential—Limited distribution to authorized persons only, pursuant to the terms of Infogix, Inc. (FKA Unitech Systems, Inc.) license agreement. This document is protected as an unpublished work and constitutes a trade secret of Infogix, Inc.

This document and the information contained herein are the property of Infogix, Inc. Reproduction or use in whole or in part of this document and the information contained herein by anyone without prior written consent of Infogix, Inc. is prohibited.

Publication Number 2653

Publication Date 12/15/15

---

# Contents

## **Chapter 1 Introduction**

Audience.....	5
Organization of Information .....	5
System Requirements .....	6
Contacting Customer Support .....	6

## **Chapter 2 Installing on the UNIX or Linux Host**

Before You Begin.....	7
System Requirements for the Host.....	8
Login and Mount the CD-ROM .....	8
Run the Setup Script .....	8
Post-Installation Instructions.....	9
Maintaining Micro Focus Licenses .....	15

## **Chapter 3 Installing the Client**

Before You Begin.....	17
System Requirements for the Client.....	18
Steps for Installing the Client .....	18

## **Chapter 4 Licensing Infogix Products**

Control File Update.....	19
Generating the TM Aggregate Transaction Report.....	22
Maintaining AppTrack Licenses.....	23

## **Chapter 5 Upgrading from a Pre-Release 4.0 Release**

Upgrading ACR/Summary for UNIX or Linux .....	26
Upgrading ACR/Detail for UNIX or Linux.....	29



---

## Introduction

This manual explains how to install ACR/Detail and ACR/Summary for UNIX or Linux and how to install and maintain your licensing. It includes instructions for installing ACR/Summary Client or ACR/Detail Client on a Windows-based machine and for upgrading to this release from a previous release.

---

**Note:** To upgrade from a release previous to Release 4.0, you must follow the instructions for your product in [Chapter 5, “Upgrading from a Pre-Release 4.0 Release”](#) on page 25.

---

If you are unsure whether you have the latest software, please contact Customer Support for verification before beginning the installation.

This chapter includes the following sections:

- [“Audience”](#) on page 5
- [“Organization of Information”](#) on page 5
- [“System Requirements”](#) on page 6
- [“Contacting Customer Support”](#) on page 6

## Audience

This guide is written for the personnel who will perform the installation. A knowledge of system installation and scripts is required.

## Organization of Information

The remaining chapters contain the following information:

[Chapter 2, “Installing on the UNIX or Linux Host”](#) provides instructions for installing ACR/Detail and ACR/Summary on the UNIX or Linux host and preparing the products for use.

[Chapter 3, “Installing the Client”](#) provides instructions for installing ACR/Summary Client or ACR/Detail Client on a Windows-based machine.

[Chapter 4, “Licensing Infogix Products”](#) explains how to establish and update your licensing and how to maintain your AppTrack licensing.

Chapter 5, “Upgrading from a Pre-Release 4.0 Release” provides instructions for upgrading ACR/Summary and ACR/Detail for UNIX or Linux from a release previous to Release 4.0.

## System Requirements

For system requirements for the host and client, see “System Requirements for the Host” on page 8 and “System Requirements for the Client” on page 18.

## Contacting Customer Support

If you need assistance, contact Infogix Customer Support.

Support Phone: +1.630.505.1890

Support Email: [support@infogix.com](mailto:support@infogix.com)

Support Website: <http://support.infogix.com>

Fax Number: +1.630.505.1883

Visit our Website: [www.infogix.com](http://www.infogix.com)

---

## Installing on the UNIX or Linux Host

This chapter describes how to install ACR/Summary and ACR/Detail on the UNIX or Linux host. It contains the following sections:

- “Before You Begin” on page 7
- “System Requirements for the Host” on page 8
- “Login and Mount the CD-ROM” on page 8
- “Run the Setup Script” on page 8
- “Post-Installation Instructions” on page 9
- “Maintaining Micro Focus Licenses” on page 15

### Before You Begin

Before you begin installation do the following:

- Verify that your UNIX or Linux system meets the requirements described in the next section.
- Make sure you have received the following:
  - The CD-ROM for installing ACR/Summary and ACR/Detail on each UNIX or Linux machine for which you are licensed.
  - The e-mail with the appropriate Micro Focus Application Server licenses. You will need this when running the setup script if this is the first time that AppTrack Licenses are being used on your system.
- Root login is required at installation for proper setup and assignment of permissions to execute ACR/Summary and ACR/Detail. Root login is not needed to run the product, e.g. acrmgr and acrgpr (see immediately below).
- An administrative account (acrmgr) and group (acrgpr) must be created to manage the resources associated to ACR/Summary and ACR/Detail. This account requires that \$HOME/bin is set in its PATH.
- Assign two ports for acrmgr communications with the client or ACR/Workbench. You may want these ports to be reserved in your global services file.

## System Requirements for the Host

The table below describes the UNIX and Linux minimum system requirements.

Vendor	Operating System	Approximate Installation Size
IBM	AIX 6.1 or higher	214 MB
Oracle	Solaris 9 or higher	65 MB
Red Hat	Linux 5.3 64 bit or higher	182 MB

## Login and Mount the CD-ROM

After logging in as root, mount the software CD-ROM. The general mount command format is:

```
mount {options} {device file} {mount point}
```

For the mount instructions for your platform, see the platform-specific sections below.

### Mounting the CD on AIX

The command is:

```
mount -v cdrfs -o ro /dev/cd0 /cdrom
```

### Mounting the CD on Solaris

The CD automatically mounts at:

```
/cdrom/cdrom0
```

### Mounting the CD on Linux

The command is:

```
mount /media/cdrom
```

## Run the Setup Script

On UNIX, run the setup script on the CD, setup.sh.

On Linux, run the command `sh ./setup.sh`.

This will prompt you through the installation.



A successful execution will produce this message:

```
*** Installation of ACR/Summary and ACR/Detail completed  
successfully. ***
```

## Post-Installation Instructions

### Ensure that Users Have Access

All users who will need access to ACR/Summary and ACR/Detail must be members of the administrative group (e.g. acrgroup).

### Automating Start/Stop of the Product Daemon (Optional)

You can use the `sdstart` and `sdstop` scripts in the administrative account's `/bin` directory to create an init script to automatically start/stop the ACR/Summary and ACR/Detail daemon at system startup/shutdown.

Login as root and use the appropriate instructions:

- “Automating Start/Stop of the Product Daemon for Linux and Solaris” on page 9.
- “Automating Start/Stop of the Product Daemon for AIX” on page 10

#### Automating Start/Stop of the Product Daemon for Linux and Solaris

1. Create the init script `sumdet` in the `init.d` directory. Use the model script `installdir/sumdet/sv/bin/sumdet`, customizing it as needed.
2. Make the script executable:
3. Create symbolic links to the `sumdet` script in the appropriate run-level script directories, as follows:

Solaris:

```
# ln -s /etc/init.d/sumdet /etc/rc0.d/K12sumdet  
# ln -s /etc/init.d/sumdet /etc/rc3.d/S97sumdet
```

Linux:

- a. Insert the following line near the top of the init script `sumdet`:

```
# chkconfig: 345 97 12
```

- b. Execute the following command:

```
# /sbin/chkconfig --add sumdet
```

## 2 ■ Installing on the UNIX or Linux Host

---

### *Post-Installation Instructions*

This completes the procedure. See the information on the `init` command in your UNIX or Linux system documentation for more information on system startup and shutdown procedures.

### **Automating Start/Stop of the Product Daemon for AIX**

Add the `sdstart` script to the `/etc/inittab` file:

```
# mkitab "acrsd:2:wait:/bin/su - $ACR_OWNER -c /$ACR_HOME/  
bin/sdstart"
```

Where:

`$ACR_OWNER` is the identifier of the administrative account (e.g. `acrmgr`) for which you want to start the daemon.

`$ACR_HOME` is the home directory for `$ACR_OWNER`.

See the information on the `init` command in your UNIX or Linux system documentation for more information on system startup and shutdown procedures.

### **Modifying the Global Environment File, `acrprf`**

ACR/Summary and ACR/Detail Server and the batch scripts require the use of an environment file, `acrprf`, to set the required variables for your site. `acrprf` was created in the administrative account's `$HOME/bin` directory and was copied to the `installdir/sumdet/sv/bin` directory. Any specific changes, as outlined below, should be made to the administrative account's `$HOME/bin/acrprf` file.

`acrprf` has four sections, which are detailed below:

- “ACR/Summary and ACR/Detail Section” on page 11
- “Modifying the ODBC Section” on page 11
- “Modifying the Oracle Section” on page 12
- “Modifying the DB2 Section” on page 13
- “Modifying the ACR/Connector Section” on page 13
- “Modifying the Visibility API Section” on page 13
- “Modifying the ACR Assure Gateway Parameters Section” on page 14

---

**Note:** Additional variables and modifications may be added to the `acrprf` file according to other products' requirements (for example, ACR/Connector or Infogix Insight).

---

### **ACR/Summary and ACR/Detail Section**

The ACR/Summary and ACR/Detail section does not require modification. All environment variables in this section are created when the Setup script has been successfully run.

### **Modifying the ODBC Section**

---

**Note:** Verify with your UNIX or Linux database administrator that the UNIX or Linux data source for your ODBC session has been set up.

---

When using ODBC, required environment variables in the ODBC section should be uncommented and modified as needed.

- ODBCUID must be set to a User ID for the specific ODBC-compliant database.
- ODBCPWD must be set to the ODBCUID's password.
- (Optional) ODBCLOC, when set, must be set to the directory where the ODBC library, libodbc, was installed. It will be used in the setup of the environment variables for the shared libraries (that is, LIBPATH, SHLIB\_PATH, and LD\_LIBRARY\_PATH). For example, `/usr/local/lib`.
- (Optional) ODBCINI, when set, must be set to the full pathname/ filename of the file with the ODBC information (usually `odbc.ini` or `.odbc.ini`).  
If it is not set, ODBC will attempt to use the system `odbc.ini` and `odbcinst.ini` files.
- (Optional) ODBCHOME is for those sites that use ODBC to connect to DB2. This variable, when set, must be set using absolute path names to the directory where the system INI file (`odbcinst.ini`) was created.

## 2 ■ Installing on the UNIX or Linux Host

---

### *Post-Installation Instructions*

- (Optional) Shared library path must be uncommented when ODBCLOC is set. Use LIBPATH for AIX and Linux and LD\_LIBRARY\_PATH for Solaris.

---

**Note: UDXODBC.so Errors:****Error #173**

Load error : file 'UDXODBC'

error code: 173, pc=0, call=1, seg=0

173 Called program file not found in drive/directory

**Error #198**

Load error : file 'UDXODBC.so'

error code: 198, pc=0, call=1, seg=0

198 Load failure

To resolve these errors, set the 1) ODBCLOC and 2) LIBPATH or LD\_LIBRARY\_PATH to the directory where the libodbc library is located, so that the ODBC drivers can be found. Also ensure that libodbc.so.1 is in this directory.

It may be helpful to do the following to get more information about an error involving UDXODBC.so:

1) Set your environment by sourcing the acrpfr file (for example, `./home/acrmgr/bin/acrpfr`).

2) Use `ldd` to check information about the shared object (e.g. `ldd UDXODBC.so`).

---

### **Modifying the Oracle Section**

When using Oracle, each environment variable in the Oracle section should be uncommented and modified as needed.

- ORACLEUID must be set to a User ID of the Oracle database.
- ORACLEPWD must be set to the ORACLEUID's password.
- ORACLE\_SID must be set to the system identifier for the Oracle database.
- ORACLE\_HOME must be set to the absolute pathname of the directory where Oracle is installed.

- (Optional) TWO\_TASK is a UNIX or Linux environment variable that can be set to a default TNS connect string. For example, you can issue the following command at the system prompt:  
% setenv TWO\_TASK test\_db.world  
When you invoke a tool such as SQL\*Plus, you would only need to type:  
% sqlplus scott/tiger  
in order to be connected to the TNS address of “test\_db.world.” Some users prefer this to typing:  
% sqlplus scott/tiger@test\_db.world  
To use TWO\_TASK, set this variable to the TNS alias for the remote instances.
- Shared library path must be uncommented. Use LIBPATH for AIX and Linux, or LD\_LIBRARY\_PATH for Solaris.

### **Modifying the DB2 Section**

When using DB2, the environment variable in the DB2 section should be uncommented and modified as needed.

DB2INSTANCE must be set to the name of your DB2 instance.

### **Modifying the ACR/Connector Section**

---

**Note:** Verify with your UNIX or Linux administrator that the UNIX or Linux data paths are set correctly.

---

When using ACR/Connector, the environment variable in the ACR connector section should be uncommented and set to the path of the created node.

Ensure to set the COBPATH variable to the ACR/Connector product installation path.

### **Modifying the Visibility API Section**

---

**Note:** Verify with your UNIX or Linux administrator that the UNIX or Linux data paths are set correctly.

---

When using the Visibility API, the environment variable in the API section should be uncommented. The JAVA\_HOME and the Visibility API install directory path must be set correctly.

## 2 ■ Installing on the UNIX or Linux Host

---

### *Post-Installation Instructions*

#### **Modifying the ACR Assure Gateway Parameters Section**

---

**Note:** Verify with your UNIX or Linux administrator that the UNIX or Linux data paths are set correctly.

---

When using the ACR Assure Gateway API, the environment variable in the ACR Assure Gateway should be uncommented. The JAVA\_HOME and the Assure Gateway API install directory path must be set correctly.

#### **Make Pre-Release 3.4 Scripts Compatible**

If you use any ACR/Summary or ACR/Detail batch scripts from Release 3.3 or before, those scripts need to access the new acrpfr environment file instead of the old acrdprf and acrsprf files. There are multiple ways of doing this, but we suggest that you create a symbolic link for acrdprf and acrsprf that points to the administrative account's \$HOME/bin/acrpfr file.

#### **Make Pre-Release 3.4 Databases Available**

If you use any ACR/Summary or ACR/Detail databases from Release 3.3 or before and you intend to access them through the Client or ACR/Workbench, the database files must allow the administrative account to read and write to them. Because each Client or Workbench user will have a user directory created in the administrative account's \$HOME directory, one approach is to copy the database files to that directory and change their ownership to the administrative account's.

#### **Increase the Maximum File Size (Optional)**

ACR/Summary or ACR/Detail ships with environment variable FILEMAXSIZE=4. This setting will be appropriate for users who always use a file input size of 4GB or less. If you use input files greater than 4GB, you will have to override this value by setting FILEMAXSIZE=8 (no limit) in the extfh configuration file.

To override the environment variable FILEMAXSIZE, create the file \$COBDIR/etc/extfh.cfg with the following contents:

```
[XFH-DEFAULT]
FILEMAXSIZE=8
```

#### **License ACR/Summary or ACR/Detail**

See Chapter 4, "Licensing Infogix Products."

## Maintaining Micro Focus Licenses

If you ever need to administer Micro Focus Application Server licenses after the setup script has run, run AppTrack via the administration script

```
installdir/license/run/mfapptrk.sh
```

and follow the prompts.

## 2 ■ Installing on the UNIX or Linux Host

---

### *Maintaining Micro Focus Licenses*



---

## Installing the Client

This chapter provides the system requirements and instructions for installing ACR/Summary Client or ACR/Detail Client on a Windows-based machine. The client provides a graphical interface for UNIX or Linux processing.

This chapter contains the following sections:

- “Before You Begin” on page 17
- “System Requirements for the Client” on page 18
- “Steps for Installing the Client” on page 18

### Before You Begin

Before you begin installation, review the following information:

Verify that the system where you plan to install the client meets the requirements described in the next section. Verify that you have the installation CD for the client you are installing:

- ACR/Summary Client
- ACR/Detail Client

### 3 ■ Installing the Client

#### *System Requirements for the Client*

---

## System Requirements for the Client

Below are the minimum system requirements for an ACR/Summary or ACR/Detail client:

Category	Requirement
<b>Hardware and Operating System</b>	IBM or compatible machine with Windows Vista, Windows 7, or Windows 2008
<b>Memory</b>	At least 100 MB of Random Access Memory (RAM)
<b>Disk Space</b>	A hard drive with at least 10 MB of free space
<b>Drive</b>	CD-ROM
<b>Network Communication</b>	Access to a network using TCP/IP protocol

## Steps for Installing the Client

You will have a separate CD for each product. The process is the same for installing an ACR/Summary Client and ACR/Detail Client, so select either of the CDs and complete the following steps.

1. Insert the installation CD into the CD-ROM drive on your PC.
2. The installation program usually starts automatically. If it does not, select Run from the Start menu and run the setup.exe program located on the installation CD.
3. The installation wizard will prompt you through the process.  
When the process completes, ACR/Summary Client or ACR/Detail Client will be installed in the Infogix program group, unless you specified a different installation directory.
4. If you purchased both clients, repeat the installation process for the remaining product.

---

## Licensing Infogix Products

This chapter discusses tasks related to licensing. This information pertains to both for UNIX and Linux. The information is divided into the following sections:

- “Control File Update” on page 19. This section tells you how to establish and update your licensing.
- “Generating the TM Aggregate Transaction Report” on page 22. This section applies only to a limited number of customers who have TM licensing.
- “Maintaining AppTrack Licenses” on page 23. This section provides instructions for maintaining your AppTrack licensing.

---

**Note:** If you are upgrading from a release previous to Release 4.0, in addition to updating your licensing, you must follow the instructions for your product in Chapter 5, “Upgrading from a Pre-Release 4.0 Release” on page 25.

---

### Control File Update

#### When to Update the Control File

The Control File controls product access in accordance with the terms of your license. There are several situations when you need to perform this update. The most common include:

- When you install ACR/Summary or ACR/Detail for the first time.
- When the terms of your license have changed.
- When you create a new control file for any reason.

---

**Note:** If you must create a new control file when upgrading from a previous release, you will be instructed to do so in the installation guide.

---

- When your license for ACR/Summary or ACR/Detail expires. If you begin receiving warning or error messages in your `SYSOUT` listing, you should follow the steps in this procedure.
- When you want to run the product(s) on a machine whose host ID is not currently included in your license.

## 4 ■ Licensing Infogix Products

### Control File Update

## Generating the Necessary Report(s)

1. Print the contents of the Control File. Go to the directory where ACR/Summary or ACR/Detail was installed (the parent directory of sumdet). Then go to the license/run directory and run the uni10pr script. This script will produce 1 or 2 reports that are required by Customer Support to generate control cards and a password for you to use in updating your Control File. The reports will be as follows:
  - The Product report (UNI10PR.rpt) displays licensing information from the associated Control File in a readable format.
  - The Transactional Measurement report (UNI10PRA.rpt) will be generated only if the Control File has ever included TM (Transactional Measurement) licensing.

**Note:** If a TM field in the Product Report has the value of N (No), the TM licensing shown in the Transactional Measurement report for that product is not currently in effect.

2. Review both reports. Following are examples of each report.

```
releasenumbr          PRODUCT REPORT  COPYRIGHT INFOGIX, INC.
DATE: 09197          PAGE: 1
TIME: 14:36         REPORT:  UNI10PR

FILENAME: /home/infogix/r40v0m00/license/files/ACRCNTL
CUSTOMER:  INFOGIX, INCORPORATED
PAGE:060  WAIT:0900  RES:Y  I-RET:0000  W-RET:0000  E-RET:4000  UPDATE:002

PRODUCT  EXP  GRACE  AUTH  TYPE  TM  HOST ID
U/JCL   99/999  60  ALL

1111112222
3333334444
5555556666
7777778888
9999990000
2222224444
2222221111
4444443333
6666665555
8888887777
0000009999
5555553333

VIOLATION:  FIRST DATE  LAST DATE  HOST ID  TYPE
            00/000    00/000
            00/000    00/000    HARDWARE
            00/000    00/000    HARDWARE
            00/000    00/000    HARDWARE

(Actual report will show information for additional products.)
```

```

releasenumbr  TRANSACTIONAL MEASUREMENT REPORT  COPYRIGHT INFOGIX, INC.
DATE: 03135                                     PAGE:          01
TIME: 15:20                                     REPORT:   UNI10PRA

CUSTOMER:      INFOGIX, INCORPORATED
PAGE:060  WAIT:0900  RES:Y  I-RET:0000  W-RET:0000  E-RET:4000  UPDATE:002

-----LICENSE-----
PRODUCT  TM  IND      VALUE      GRACE  RESET      VALUE
U/SUM   RULD EXEC          5,000        40   03/135     5,060
-----VIOLATION PER LICENSE INTERVAL-----
FIRST   LAST      VALUE      COUNT
03/135  03/135     5,050        3
-----VIOLATION PER CHANGE OF LICENSE VALUE-----
FIRST   LAST      MAXIMUM VALUE  TOTAL
03/010  03/135           5,100        50

-----LICENSE-----
PRODUCT  TM  IND      VALUE      GRACE  RESET      VALUE
U/SUM   RULM EXEC          150,000        40   03/130     10,000
-----VIOLATION PER LICENSE INTERVAL-----
FIRST   LAST      VALUE      COUNT
00/000  00/000         0          0
-----VIOLATION PER CHANGE OF LICENSE VALUE-----
FIRST   LAST      MAXIMUM VALUE  TOTAL
00/000  00/000         0          0

-----LICENSE-----
PRODUCT  TM  IND      VALUE      GRACE  RESET      VALUE
U/SUM   RECD EXEC          100 (IN 000S)  20   03/135     90,000
-----VIOLATION PER LICENSE INTERVAL-----
FIRST   LAST      VALUE      COUNT
00/000  00/000         0          0
-----VIOLATION PER CHANGE OF LICENSE VALUE-----
FIRST   LAST      MAXIMUM VALUE  TOTAL
00/000  00/000         0          0
(Actual report may show information for additional TM types and additional products.)

```

3. Request your control cards and password: Using the information in “Contacting Customer Support” on page 6, do the following:
  - Call Customer Support to request the appropriate control cards and password based on your license agreement. Indicate if there are any special considerations. For example, let them know if you are running a disaster recovery test.
  - E-mail or FAX the reports generated in the previous step to Customer Support. Customer Support will FAX or e-mail you a set of text input records which consist of your control card(s) and password.

## Performing the Update

1. Create a file called `update.txt` in the `license/run` directory and paste in the control card(s) and password from the e-mail or enter them from the FAX.
2. Save the file and run the `unicf50` script with the following command:

```
unicf50 update.txt
```

## 4 ■ Licensing Infogix Products

### Generating the TM Aggregate Transaction Report

3. Verify the update by reviewing the Control File Update report (UNIFAX.rpt) that is output by the `unicf50` script. If the update completed successfully, the report should contain the message UPDATE COMPLETE. If the report shows that any of the control cards failed, print and FAX or e-mail the report to Customer Support for assistance.

Following is an example of the report showing a successful update.

```
CHANGE ID: 111111222202340017
UNICF: /home/infogix/license/files/ACRCNTL.dat
ACCEPTED USUMJOBV20000 00000000000000
ACCEPTED USUMINPDV20000 00000000000000
ACCEPTED USUMRECDV20000 00000000000000
ACCEPTED UDRSJOBV20000 00000000000000
ACCEPTED UDRSINPDV20000 00000000000000
ACCEPTED UDRSRECDV20000 00000000000000
ACCEPTED PW0000*****000000
*****REQUEST PHASE COMPLETE*****
CHANGED USUMJOBV20000 00000000000000
CHANGED USUMINPDV20000 00000000000000
CHANGED USUMRECDV20000 00000000000000
CHANGED UDRSJOBV20000 00000000000000
CHANGED UDRSINPDV20000 00000000000000
CHANGED UDRSRECDV20000 00000000000000
UPDATE COMPLETE
```

## Generating the TM Aggregate Transaction Report

The TM Aggregate Transaction report is an encrypted report that you run at the request of a member of the Customer Development and/or Market Development team. The report prints aggregate counts for each transaction type that is being tracked (jobs, input sources, records, and/or rules). After you e-mail the report to the requestor at Infogix, it is decrypted and used for the following purposes:

- To aid in analyzing your transaction usage.
- To implement actual transaction usage licensing where you are billed on a “pay as you go” basis.

## Generating the Report

The requestor will let you know which of the following options to use in generating the report. Generate the report by executing the uni20tm script with the requested option. The script is located in license/run directory. The options are as follows:

Option	Purpose
uni20tm "ALL P"	Prints the aggregate counts for both ACR/Summary and ACR/Detail.
uni20tm "ALL R"	Prints the aggregate counts and resets the counters for both ACR/Summary and ACR/Detail.
uni20tm "USUMP"	Prints the aggregate counts for ACR/Summary only.
uni20tm "USUMR"	Prints the aggregate counts and resets the counters for ACR/Summary only.
uni20tm "UDRSP"	Prints the aggregate counts for ACR/Detail only.
uni20tm "UDRSR"	Prints the aggregate counts and resets the counters for ACR/Detail only.

The name of the generated report will be UNITMRPT.rpt. After running the report you will receive a display showing the contents of the file (the report) and the location that the file was written to.

The report will be similar to the following example, which shows the left end of the report:

```
01R99UC47.UNI.UNICF                               INFOGIX, INCORPORATED
02CFLNFGHIJABCDEFGHIJABDEFGHIJBCDEFGHIJBBCEFGHIJBCDEFGHMJABCDEFGHIJBCDEFHH
02FKMEFGHIJABCDEFGHIJABCDEFGHIJABCDEFGHIJABCDEFGHIJABCDEFGHIJABCDEFGHIJABCDEFGHI
```

After running the report, e-mail it to the requestor at Infogix.

## Maintaining AppTrack Licenses

In addition to Infogix's Control File, Application Server licenses must be installed for ACR/Detail and ACR/Summary to run successfully. The initial licenses are generally entered when the product is being installed and prepared for use. However, there may be times when you wish to obtain license information or perform further maintenance. You may do this by running the Application Server License Administration System, which is known as AppTrack. Go to the ../license/run directory (where ACR/Detail

## 4 ■ Licensing Infogix Products

---

### *Maintaining AppTrack Licenses*

or ACR/Summary is installed) and execute mfapptrk.sh. You will be presented with the following menu through which you can perform all administration functions:

```
Application Server License Administration System - AppTrack
-----
1.  License List
2.  License Summary
3.  License Install
4.  License Uninstall
5.  Change/Set Password
6.  Reinitialize Licensing
7.  Current Users
9.  Quit
Enter the Menu Selection
```

Choices 1, 2, and 7 will provide information about your installed licenses and their use.

Choices 3 and 4 will allow you to add or delete licenses.

Choice 5 will allow you to maintain a password on this Administration System.

Choice 6 will refresh the AppTrack license database.

Choice 9 will let you exit the utility.



---

## Upgrading from a Pre-Release 4.0 Release

This chapter provides instructions required for upgrading ACR/Summary and ACR/Detail for UNIX or Linux from a release previous to Release 4.0.

Release 4.0 provides extended internal items, which increase the maximum extractable length for numeric data from 15 to 30 digits, and for text data from 8 to 80 characters. The upgrade procedures described here expand your definition and history databases to make room for these new items.

ACR/Summary and ACR/Detail each have two expansion utilities for this purpose: one for expanding the history database and another for expanding the definition database. The utilities and sample scripts for running them are included with the current release of ACR/Summary and ACR/Detail.

To run the expansion utilities, you need to know how to edit and execute scripts.

---

**Note:** These upgrade procedures should be followed after you have installed the new release and updated your license based on the instructions in the preceding chapters.

---

This document contains the following sections:

- “Upgrading ACR/Summary for UNIX or Linux” on page 26
- “Upgrading ACR/Detail for UNIX or Linux” on page 29

# Upgrading ACR/Summary for UNIX or Linux

## Expanding the History Database for ACR/Summary

The ACR/Summary History Expansion Utility (sumexphf.sh) copies and expands pre-release 4.0 history data into a history database for Release 4.0 or higher.

This utility produces a display that lists any system output messages.

The steps for editing and running sumexphf.sh are as follows:

1. Make a copy of the sumexphf.sh file for modification. Do not modify the original template.

---

**Warning:** It is very important that you perform the expansion on a copy of sumexphf.sh, and keep the original as a backup.

---

The .sh file will be in [INSTALLDIR]/sumdet/scripts or [ACRMGR]/scripts.

2. Open the copy you made of sumexphf.sh file and perform the following edits:

---

**Warning:** You MUST make these edits before running the .sh file.

---

- a. Edit the ACRWRK environment variable. Replace ?????? with the full pathname of the directory where the ACR/Summary history database is located.

```
#
-----
# Set the default working directory:
#   e.g. ACRWRK=/home/userid
#-----
ACRWRK=?????? ; export ACRWRK
```

- b. In the required files section, define the following files that are input and output of the utility:

```
#-----
# Define required files
#-----
dd_UNIHFOLD=$ACRWRK/????????? ; export dd_UNIHFOLD
#pre r4.0 history database
dd_UNIHF=$ACRWRK/????????? ; export dd_UNIHF
#history database
```

**dd\_UNIHFOLD:** Replace ?????? with the name of the pre-Release 4.0 ACR/Summary history database file that contains the history data you want to copy/expand.

dd\_UNIHF: Replace ?????? with the path and name of the new ACR/Summary history database file.

3. Save your changes and run sumexphf.sh.
4. Check the display for any error messages.

## Expanding the Definition Database for ACR/Summary

The ACR/Summary Definition Expansion Utility (sumexpdf.sh) copies and expands pre-release 4.0 definition data into a definition database for Release 4.0 or higher.

This utility produces a display that lists any system output messages.

The steps for editing and running sumexpdf.sh are as follows:

1. Make a copy of the sumexpdf.sh file for modification. Do not modify the original template.

---

**Warning:** It is very important that you perform the expansion on a copy of sumexpdf.sh, and keep the original as a backup.

---

The .sh file will be in [INSTALLDIR]/sumdet/scripts or [ACRMGR]/scripts.

2. Open the copy you made of sumexpdf.sh and make the following edits:

---

**Warning:** You MUST make these edits before running the .sh file.

---

- a. Edit the ACRWRK environment variable. Replace ?????? with the full pathname of the directory where the ACR/Summary definition database is located.

```
#-----
# Set the default working directory:
#   e.g. ACRWRK=/home/userid
#-----
ACRWRK=??????                ; export ACRWRK
```

## 5 ■ Upgrading from a Pre-Release 4.0 Release

### Upgrading ACR/Summary for UNIX or Linux

---

- b. In the required files section, define the following files that are input and output of the utility:

```
#-----  
# Define required files  
#-----  
dd_UNIDFOLD=$ACRWRK/????????? ; export dd_UNIDFOLD  
#pre r4.0 definition database  
dd_UNIDF=$ACRWRK/????????? ; export dd_UNIDF  
#definition database
```

dd\_UNIDFOLD: Replace ?????? with the name of the pre-Release 4.0 ACR/Summary definition database file that contains the definition data you want to copy/expand.

dd\_UNIDF: Replace ?????? with the path and name of the new ACR/Summary definition database file.

3. Save your changes and run sumexpdf.sh.
4. Check the display for any error messages.

### Optional: Update Job Output Options

If you are using ACR/Workbench or ACR/Summary Client, you may want to change the default for printing extended internal items as described below.

For existing (pre-release 4.0) jobs, the default for the Extended Internal Items option in the Job Output Options dialog box is Do not print. This means that the Extended Internal Items section will not be included in the Control Report for those jobs.

(For new jobs created after the upgrade to Release 4.0 or higher, the default for this option will be Print.)

If your site wants the Extended Internal Items section to print in the Control Report for one or more existing jobs that you plan to use after the upgrade, you need to make a change to the job output options for each of those jobs as follows:

1. Open ACR/Summary.
2. Open the job.
3. Select Print Control Reports.
4. Change the Extended Internal Items option to Print.

## Upgrading ACR/Detail for UNIX or Linux

### Expanding the History Database for ACR/Detail

The ACR/Detail History Expansion Utility (detexphf.sh) copies and expands pre-release 4.0 history data into a history database for Release 4.0 or higher.

This utility produces a display that lists any system output messages.

The steps for editing and running detexphf.sh are as follows:

1. Make a copy of the detexphf.sh file for modification. Do not modify the original template.

---

**Warning:** It is very important that you perform the expansion on a copy of detexphf.sh, and keep the original as a backup.

---

The .sh file will be in [INSTALLDIR]/sumdet/scripts or [ACRMGR]/scripts.

2. Open the copy you made of detexphf.sh file and make the following edits:

---

**Warning:** You MUST make these edits before running the .sh file.

---

- a. Edit the ACRWRK environment variable. Replace ????? with the full pathname of the directory where the ACR/Detail history database is located.

```
#-----
# Set the default working directory:
#   e.g. ACRWRK=/home/userid
#-----
ACRWRK=?????; export ACRWRK
```

- b. In the required files section, define the following files that are input and output of the utility:

```
#-----
# Define required files
#-----
dd_UNIHFOLD=$ACRWRK/?????????; export dd_UNIHFOLD
#pre r4.0 history database
dd_UNIHF=$ACRWRK/?????????; export dd_UNIHF
#history database
```

## 5 ■ Upgrading from a Pre-Release 4.0 Release

### Upgrading ACR/Detail for UNIX or Linux

---

dd\_UNIHFOLD: Replace ?????? with the name of the pre-Release 4.0 ACR/Detail history database file that contains the history data you want to copy/expand.

dd\_UNIHF: Replace ?????? with the path and name of the new ACR/Detail history database file.

3. Save your changes and run `detexphf.sh`.
4. Check the display for any error messages.

### Expanding the Definition Database for ACR/Detail

The ACR/Detail Definition Expansion Utility (`detexpdf.sh`) copies and expands pre-release 4.0 definition data into a definition database for Release 4.0 or higher.

This utility produces a display that lists any system output messages.

The steps for editing and running `detexpdf.sh` are as follows:

1. Make a copy of the `detexpdf.sh` file for modification. Do not modify the original template.

---

**Warning:** It is very important that you perform the expansion on a copy of `detexpdf.sh`, and keep the original as a backup.

---

The `.sh` file will be in `[INSTALLDIR]/sumdet/scripts` or `[ACRMGR]/scripts`.

2. Open the copy you made of `detexpdf.sh` file and perform the following edits:

---

**Warning:** You MUST make these edits before running the `.sh` file.

---

- a. Edit the `ACRWRK` environment variable. Replace ?????? with the full pathname of the directory where the ACR/Detail history database is located.

```
#-----  
# Set the default working directory:  
#   e.g. ACRWRK=/home/userid  
#-----  
ACRWRK=?????? ; export ACRWRK
```

- b. In the required files section, define the following files that are input and output of the utility:

```

#-----
# Define required files
#-----
dd_UNIDFOLD=$ACRWRK/????????? ; export dd_UNIDFOLD
#pre r4.0 definition database
dd_UNIDF=$ACRWRK/????????? ; export dd_UNIDF
#definition database

```

**dd\_UNIDFOLD:** Replace ?????? with the name of the pre-Release 4.0 ACR/Detail definition database file that contains the definition data you want to copy/expand.

**dd\_UNIDF:** Replace ?????? with the path and name of the new ACR/Detail definition database file.

3. Save your changes and run `detexpdf.sh`.
4. Check the display for any error messages.

## 5 ■ Upgrading from a Pre-Release 4.0 Release

---

*Upgrading ACR/Detail for UNIX or Linux*